

# Land surface Verification Toolkit

## LVT 7.2 Users' Guide

May 6, 2017

Revision 1.3

### History:

Revision	Summary of Changes	Date
1.3	LVT 7.2 public release	May 6, 2015



**National Aeronautics and Space Administration**  
**Goddard Space Flight Center**  
Greenbelt, Maryland 20771

History:

Revision	Summary of Changes	Date
1.2	Update lvt.config documentation	May 12, 2015
1.1	LVT 7.1 AFWA rp2	May 11, 2015
1.0	LVT 7.1 public release	April 24, 2015

# Contents

<b>1</b>	<b>Introduction</b>	<b>8</b>
1.1	What's New . . . . .	8
1.1.1	Version 7.2 . . . . .	8
1.1.2	Version 7.1 . . . . .	9
1.1.3	Version 7.0 . . . . .	9
1.1.4	Version 1.2 . . . . .	10
1.1.5	Version 1.1 . . . . .	11
1.1.6	Version 1.0 . . . . .	11
<b>2</b>	<b>Background</b>	<b>12</b>
2.1	LVT . . . . .	12
2.2	Summary of key features . . . . .	12
<b>3</b>	<b>Preliminary Information</b>	<b>14</b>
<b>4</b>	<b>Obtaining the Source Code</b>	<b>15</b>
4.1	Important Note Regarding File Systems . . . . .	15
4.2	Public Release Source Code Tar File . . . . .	15
4.3	Checking Out the Source Code . . . . .	16
<b>5</b>	<b>Building the Executable</b>	<b>17</b>
5.1	Development Tools . . . . .	17
5.2	Required Software Libraries . . . . .	17
5.3	Optional Software Libraries . . . . .	18

5.4	Build Instructions . . . . .	19
5.5	Generating documentation . . . . .	21
<b>6</b>	<b>Running the Executable</b>	<b>23</b>
<b>7</b>	<b>LVT config File</b>	<b>24</b>
7.1	Overall driver options . . . . .	24
7.2	Domain specification . . . . .	29
7.2.1	LVT run domain . . . . .	30
7.3	Analysis options specification . . . . .	31
7.4	Data stream sources . . . . .	43
7.4.1	LIS output . . . . .	43
7.4.2	AGRMET data . . . . .	48
7.4.3	ALEXI data . . . . .	48
7.4.4	Ameriflux station observations . . . . .	49
7.4.5	ANSA snow depth data . . . . .	49
7.4.6	ANSA SWE data . . . . .	50
7.4.7	ARM station observations . . . . .	50
7.4.8	USDA ARS soil moisture observations . . . . .	51
7.4.9	SNODAS snow analysis data . . . . .	52
7.4.10	CPC precipitation data . . . . .	52
7.4.11	ESA CCI soil moisture data . . . . .	53
7.4.12	Gridded FLUXNET data . . . . .	53
7.4.13	Global Change Observation Mission – Water (GCOMW)	53

7.4.14	Global Historic Climatology Network (GHCN) data . . .	53
7.4.15	GlobSnow data . . . . .	54
7.4.16	ISMN soil moisture observations . . . . .	54
7.4.17	LPRM AMSR-E soil moisture retrievals . . . . .	54
7.4.18	MOD16A2 data . . . . .	55
7.4.19	MODIS LST . . . . .	55
7.4.20	North American Soil Moisture Database (NASMD) . . . .	55
7.4.21	Naturalized monthly streamflow data . . . . .	55
7.4.22	NLDAS2 . . . . .	56
7.4.23	Soil Moisture Operational Processing System (SMOPS) .	57
7.4.24	SMOS L1 TB . . . . .	58
7.4.25	SMOS L2 soil moisture . . . . .	58
7.4.26	SNODEP metobs snow depth data . . . . .	58
7.4.27	SNOTEL SWE observations . . . . .	58
7.4.28	SURFRAD observations (radiation, wind speed, pressure)	59
7.4.29	SCAN soil moisture observations . . . . .	59
7.4.30	USGS ground water . . . . .	60
7.4.31	USGS daily streamflow data . . . . .	60
7.4.32	University of Washington ET data . . . . .	61
7.4.33	GIMMS AVHRR NDVI data . . . . .	61
7.4.34	GIMMS MODIS NDVI data . . . . .	61
7.4.35	GLDAS version 2 data . . . . .	61
7.4.36	MERRA version 2 data . . . . .	62

7.4.37	ERA Interim Land data . . . . .	62
7.4.38	SSEB operational data . . . . .	62
7.4.39	GRDC data . . . . .	62
7.4.40	LIS DAOBS output as the observation . . . . .	63
7.4.41	ISCCP land surface temperature observations . . . . .	63
7.4.42	LSWG Tb observations . . . . .	64
7.4.43	FMI SWE observations . . . . .	65
7.4.44	CMC daily snow depth observations . . . . .	65
7.4.45	NASA AMSR-E soil moisture retrievals . . . . .	65
7.4.46	AMMA station observations . . . . .	65
7.4.47	SMOSREX in-situ soil moisture observations . . . . .	67
7.4.48	MOD10A1 snow cover data . . . . .	67
7.4.49	GRACE (processed from LDT) data . . . . .	67
7.4.50	CEOP . . . . .	68
7.4.51	COOP . . . . .	68
7.4.52	Great Lakes Environmental Research Lab (GLERL) . . . . .	69
7.4.53	GSOD . . . . .	69
7.4.54	Plate Boundary Observatory H2O (PBOH2O) . . . . .	69
7.4.55	WG PBMR . . . . .	70
7.4.56	GLEAM . . . . .	70
7.4.57	FLUXNET2015 . . . . .	70
7.4.58	USCRN soil moisture . . . . .	71
7.4.59	WG SWRC . . . . .	71

7.5	OptUE processing options . . . . .	71
7.6	DA diagnostics analysis . . . . .	73
7.7	DA observation analysis . . . . .	74
<b>8</b>	<b>Configuration of metrics</b>	<b>75</b>
<b>9</b>	<b>Model Output Specifications</b>	<b>78</b>
<b>A</b>	<b>How to verify a “non-LIS” dataset?</b>	<b>83</b>
<b>B</b>	<b>Description of output files from LVT</b>	<b>84</b>
B.0.1	METADATA files . . . . .	84
B.0.2	Stats summary file . . . . .	85
B.0.3	ASCII Time Series files . . . . .	86
B.0.4	Domain time Series files (Binary/NETCDF) . . . . .	87
B.0.5	Final domain files (Binary/NETCDF) . . . . .	87

# 1 Introduction

This is the User's Guide for Land surface Verification Toolkit (LVT;[1]). This document describes how to download and install LVT codes and instructions on building an executable.

This document consists of several sections, described as follows:

- 1 Introduction:** the section you are currently reading
- 2 Background:** general information about the LVT
- 3 Preliminary Information:** general information, steps, instructions, and definitions used throughout the rest of this document
- 4 Obtaining the Source Code:** the steps needed to download the source code
- 5 Building the Executable:** the steps needed to build the LVT executable
- 6 Running the Executable:** the steps needed to run the LVT executable
- 7 LVT config File:** describes the user-configurable options
- 8 Configuration of metrics:** describes the specification of various metrics in LVT.
- 9 Model Output Specifications:** describes the specification of the model output from LIS.

## 1.1 What's New

### 1.1.1 Version 7.2

1. Supports new data streams
  - datastreams/CMORPH
  - datastreams/Daymet
  - datastreams/FLUXNETmte
  - datastreams/GCOMW\_AMSR2L3snd
  - datastreams/GIMMS\_MODIS\_NDVI
  - datastreams/GLDAS1
  - datastreams/GOES\_LST

- datastreams/GOME2\_SIF
- datastreams/JULESdata
- datastreams/LIS6out
- datastreams/LISDAdiag
- datastreams/LVTpercentile
- datastreams/MERRA-Land
- datastreams/SCANGMAO
- datastreams/simGRACE
- datastreams/SMAPsm
- datastreams/SMAPTb
- datastreams/SMOS\_CATDS\_L3sm
- datastreams/SMOS\_NESDIS
- datastreams/SNODEP
- datastreams/USCRNsm
- datastreams/USDM
- datastreams/USGS\_streamflow\_gridded

### 1.1.2 Version 7.1

1. Supports Global Change Observation Mission - Water (GCOMW) observations
2. Supports Advanced Scatterometer (ASCAT) data
3. Supports Soil Moisture and Ocean Salinity (SMOS) observations
4. Supports Soil Moisture and Ocean Salinity (SMOS) L1 Tb observations
5. Supports MODIS LST data
6. Supports Great Lakes Hydro data
7. Supports time lagged computations

### 1.1.3 Version 7.0

Note that LVT has been renumbered to version 7.0.

1. Supports NLDAS-2 SAC datasets, including the post-processed SAC soil moisture on Noah levels

2. Supports the capability to compute metrics on a basin/region scale rather than on a pixel-by-pixel basis.
3. Supports the capability to process USGS ground water well data
4. Supports the capability to process Plate Boundary Observatory data (snow depth and soil moisture)
5. Supports the North American Soil Moisture Database (NASMD) data
6. Supports the ALEXI data
7. Supports the metric to compute percentiles for each ensemble member separately
8. Supports GRACE observations (these are the "processed" GRACE observations generated by LDT)
9. Supports the UW ET data
10. Supports the options for restart for SRI, SPI, SSWI and percentile calculations
11. Supports metric called SGWI - standardized ground water index — which is similar to SSWI, but for TWS variable
12. Support for a number of ratio variables are added:
  - SWE/P (snow water equivalent over precip)
  - ET/P (evapotranspiration over precip)
  - Qs/P (surface runoff over precip)
  - Qsb/P (subsurface runoff over precip)
13. Supports the river flow variate metric
14. Supports metrics for computing min, max and sum
15. Support to read LIS DA processed observations

#### 1.1.4 Version 1.2

1. Updates related to OptUE processing

### **1.1.5 Version 1.1**

1. Added the plugin for processing processed LIS DA observations
2. Removed the FEWSNET SOS processing metric
3. Added plugins for NLDAS2, Natural streamflow
4. Updated to provide backwards support for LIS 6.1.

### **1.1.6 Version 1.0**

1. This is the initial version developed for evaluating output from LIS version 6.0 or higher.

## 2 Background

Verification and evaluation are essential processes in the development and application of simulation models. The Land surface Verification Toolkit (LVT) is an integrated framework designed specifically for evaluating land surface model (LSM) outputs. The system was originally designed as a post processor to the NASA Land Information System (LIS), which is an integrated framework to conduct multi-model land surface model simulations and data assimilation integrations. LVT also includes the capabilities to convert any land surface-specific dataset to a “LIS output format/style”, thus enabling cross-comparisons of a broad set of land surface datasets (in-situ, remotely sensed, and reanalysis products).

### 2.1 LVT

LVT provides a formal system for LSM output evaluation and verification. The capabilities of LVT also provides a tool to systematically evaluate and benchmark LSM performance and the impact of computational enhancements such as data assimilation. LVT includes a range of both deterministic and probabilistic verification measures, with similarity-based and object-based methods in development.

LVT is designed as an object oriented framework, with a number of points of flexibility known as “plugins”. Specific implementations are added to the framework through the plugin-interfaces. LVT uses the plugin-based architecture to support the processing of different types of observational data sets, ranging from in-situ, satellite and remotely sensed and reanalysis products.

In addition to providing methods for model output verification, LVT also provides capabilities to analyze the outputs from LIS data assimilation (LIS-DA) and the LIS optimization and uncertainty estimation (LIS-OPTUE) subsystems.

### 2.2 Summary of key features

The key capabilities of LVT can be summarized as follows:

- Capability to convert a given dataset to “LIS-style format”
- A text-based, configurable input interface
- Supports a broad range of in-situ, remotely-sensed and reanalysis data products. For e.g.:

- Surface fluxes - Ameriflux, ARM, CEOP, AMMA
  - Soil moisture - SCAN, SMOSREX, AMSR-E retrievals
  - Snow - COOP, GSOD, SNODAS, SNODEP, CMC, FMI, GlobSnow, SNOTEL
  - LST - ISCCP
  - Radiation - SURFRAD
- A number of deterministic and probabilistic verification measures. E.g. RMSE, Bias, Correlations, POD, FAR, etc.
  - Supports the computation of land surface model diagnostics and closure checks. E.g.: Energy, water balance checks, seasonal and average diurnal cycles
  - Options of time series extraction of individual grid points and area averages
  - Options of temporal averaging. E.g. : Comparisons at hourly, daily, monthly scales
  - Options for data masking. E.g. Apply an external mask to the comparisons, apply thresholds on the comparisons
  - Supports the analysis of outputs from LIS-OPTUE and LIS-DA subsystems. For e.g: Analysis of normalized innovations from LIS-DA

### 3 Preliminary Information

This section provides some preliminary information to make reading this guide easier.

Commands are written with a fixed-width font. E.g.:

```
% cd /path/to/LVT
% ls
“...compiler flags, then run gmake.”
```

File names are written in italics. E.g.:

```
/path/to/LVT/src
```

You need to create a working directory on your system to install LVT. Let's call this directory */path/to/LVT/*. Throughout the rest of this document, this directory shall be referred to as *\$WORKING*. You should create a directory to run LVT in. This directory can be created anywhere on your system, but, in this document, we shall refer to this running directory as *\$WORKING/run*.

## 4 Obtaining the Source Code

This section describes how to obtain the source code needed to build the LVT executable.

Beginning with LIS public release 7.1rp1, the LIS and LVT source code is available as open source under the NASA Open Source Agreement (NOSA). Please see LIS' web-site for a copy the NOSA.

Due to the history of LVT's development, prior versions of the LVT source code may not be freely distributed. That older source code is available only to U.S. government agencies or entities with a U.S. government grant/contract. LIS' web-site explains how qualified persons may request a copy of the older source code.

### 4.1 Important Note Regarding File Systems

LVT is developed on Linux/Unix platforms. Its build process expects a case sensitive file system. Please make sure that you unpack and/or 'svn checkout' the LVT code into a directory within a case sensitive file system. In particular, if you are using LVT within a Linux-based virtual machine hosted on a Windows or Macintosh system, do not compile/run LVT from within a shared folder. Move the LVT source code into a directory within the virtual machine.

### 4.2 Public Release Source Code Tar File

The LVT 7.2 source code is available for download as a tar-file from LIS' web-site. All users are encouraged to fill in the Registration Form and join the mailing list, both also accessible from LIS' web-site. After downloading the LVT tar-file:

1. Create a directory to unpack the tar-file into. Let's call it *TOPLEVELDIR*.
2. Place the tar-file in this directory.  

```
% mv LVT_public_release_7.2r.tar.gz TOPLEVELDIR
```
3. Go into this directory.  

```
% cd TOPLEVELDIR
```
4. Run `gzip -dc LVT_public_release_7.2r.tar.gz | tar xf -`  
This command will unzip and untar the tar-file.

Note that the directory containing the LVT source code will be referred to as *\$WORKING* throughout the rest of this document.

### 4.3 Checking Out the Source Code

The source code is maintained in a Subversion repository. Only developers may have access to the repository. Developers must use the Subversion client (`svn`) to obtain the LVT source code. If you need any help regarding Subversion, please go to <http://subversion.apache.org/>.

Developers must first obtain access to the LVT source code repository. To obtain access you must contact the LVT team. Once you have access to the repository, you will be given the correct Subversion command to run to checkout the source code.

1. Create a directory to checkout the code into. Let's call it *TOPLEVELDIR*.

2. Go into this directory.

```
% cd TOPLEVELDIR
```

3. Check out the source code into a directory called *src*.

For the public version, run the following command:

```
% svn checkout https://progress.nccs.nasa.gov/svn/lis/tools/lvt/7/public7.2  
src
```

Note that the directory containing the LVT source code will be referred to as *\$WORKING* throughout the rest of this document.

Source code documentation may be found on LVT's web-site. Follow the "Documentation" link.

## 5 Building the Executable

This section describes how to build the source code and create LVT's executable: named LVT.

### 5.1 Development Tools

This code has been compiled and run on Linux PC (Intel/AMD based) systems and Cray systems. These instructions expect that you are using such a system. In particular you need:

- Linux
  - Compilers
    - \* either Intel Fortran Compiler versions 14 or 15 with corresponding Intel C Compiler
    - \* or GNU's Compiler Collection 4.9.2, both gfortran and gcc
  - GNU's make, gmake, version 3.77 or 3.81
  - perl, version 5.10
- Cray/Linux
  - either Intel Fortran Compiler versions 14 or 15 with corresponding Intel C Compiler
  - GNU's make, gmake, version 3.77 or 3.81
  - perl, version 5.10

### 5.2 Required Software Libraries

In order to build the LVT executable, the following libraries must be installed on your system:

- Earth System Modeling Framework (ESMF) version 5.2.0rp3 (or higher). (<http://www.earthsystemmodeling.org/download/releases.shtml>)  
Please read the ESMF User's Guide for details on installing ESMF with MPI support and without MPI support ("mpiuni").  
Note that starting with ESMF version 5, the ESMF development team is trying to maintain backwards compatibility with its subsequent releases. The LIS development team, however, has neither compiled nor tested against versions of ESMF newer than 5.2.0rp3.

### 5.3 Optional Software Libraries

The following libraries are not required to compile LVT. They are used to extend the functionality of LVT.

- GRIB-API version 1.12.3 (or higher).  
(<https://software.ecmwf.int/wiki/display/GRIB/Home>)  
GRIB-API is developed by ECMWF and supports both grib1 and grib2 formats.  
Note that GRIB-API requires the JasPer library (<http://www.ece.uvic.ca/frodo/jasper/>).

- NetCDF either version 3.6.3 or version 4.3.0 (or higher).  
(<http://www.unidata.ucar.edu/software/netcdf/>)

Please read the on-line documentation for details on installing NetCDF.

Additional notes for NetCDF 4:

- You must also choose whether to compile with compression enabled. Compiling with compression enabled requires HDF 5 and zlib libraries. To enable compression, add `--enable-netcdf-4` to the `configure` options. To disable compression, add `--disable-netcdf-4` to the `configure` options.

An example of installing NetCDF 4 without compression:

```
% ./configure --prefix=$HOME/local/netcdf-4.3.0 --disable-netcdf-4
% make
% make install
```

An example of installing NetCDF 4 with compression:

```
% CPPFLAGS=-I$HOME/local/hdf5/1.8.11/include \
> LDFLAGS=-L$HOME/local/hdf5/1.8.11/lib \
> ./configure --prefix=$HOME/local/netcdf/4.3.0 --enable-netcdf-4
% make
% make install
```

- You must also download the *netcdf-fortran-4.2.tar.gz* file. First install the NetCDF C library, then install the NetCDF Fortran library. Again, please read the on-line documentation for more details.

An example of installing the NetCDF 4 Fortran library:

```
% LD_LIBRARY_PATH=$HOME/local/netcdf/4.3.0/lib:$LD_LIBRARY_PATH \
> CPPFLAGS=-I$HOME/local/netcdf/4.3.0/include \
> LDFLAGS=-L$HOME/local/netcdf/4.3.0/lib \
> ./configure --prefix=$HOME/local/netcdf/4.3.0
% make
% make install
```

- HDF

You may choose either HDF version 4, HDF version 5, or both.

HDF is used to support a number of remote sensing datasets.

If you wish to use MODIS snow cover area observations or NASA AMSR-E soil moisture observations, then you need HDF 4 support.

If you wish to use ANSA snow cover fraction observations, then you need HDF 5 support.

If you wish to use PMW snow observations, then you need both HDF 4 and HDF 5 support.

- HDF 4

If you choose to have HDF version 4 support, please download the HDF source for version 4.2r4 (or later) from (<http://www.hdfgroup.org/products/hdf4>) and compile the source to generate the HDF library. Make sure that you configure the build process to include the Fortran interfaces by adding the `--enable-fortran` option to the `configure` command.

Note that HDF4 contains its own embedded version of NetCDF. You must disable this support by adding the `--disable-netcdf` option to the `configure` command.

Note that when compiling LVT with HDF 4 support, you must also download and compile HDF-EOS2 (<http://hdfeos.org/>).

- HDF 5

If you choose to have HDF version 5 support, please download the HDF source for version 1.8.11 (or later) from (<http://www.hdfgroup.org/HDF5/>) and compile the source to generate the HDF library. Make sure that you configure the build process to include the Fortran interfaces by adding the `--enable-fortran` option to the `configure` command.

To install these libraries, follow the instructions provided at the various URL listed above. Please note that though GRIB-API and NETCDF are optional, they are highly recommended as the functionality of LVT will be hugely reduced without these two libraries.

## 5.4 Build Instructions

1. Perform the steps described in Section 4 to obtain the source code.
2. Goto the `$WORKING/src/` directory. This directory contains two scripts for building the LVT executable: `configure` and `compile`.
3. Set the `LVT_ARCH` environment variable based on the system you are using. The following commands are written using Bash shell syntax.

- For an AIX system  
% export LVT\_ARCH=AIX
- For a Linux system with the Intel Fortran compiler  
% export LVT\_ARCH=linux\_ifc
- For a Linux system with the Absoft Fortran compiler  
% export LVT\_ARCH=linux\_absoft
- For a Linux system with the Lahey Fortran compiler  
% export LVT\_ARCH=linux\_lf95

It is suggested that you place this command in your *.profile* (or equivalent) startup file.

4. Run the *configure* script first by typing:

```
% ./configure
```

This script will prompt the user with a series of questions regarding support to compile into LVT, requiring the user to specify the locations of the required and optional libraries via several LVT specific environment variables. The following environment variables are used by LVT.

Variable	Description
LVT_SRC	Location of the LVT source tree ( <i>\$WORKING/src/</i> )
LVT_ARCH	LVT architecture (See below)
LVT_FC	Fortran compiler to be used ( <i>mpif90</i> , if mpi is installed)
LVT_CC	C compiler to be used ( <i>mpicc</i> , if mpi is installed)
LVT_GRIBAPI	path to grib api library
LVT_NETCDF	path to NETCDF library
LVT_HDF4	path to HDF4 library
LVT_HDF5	path to HDF5 library
LVT_HDFEOS	path to HDFEOS library
LVT_MODESMF	path to ESMF header files
LVT_LIBESMF	path to ESMF library files

Note that the *CC* variable must be set to a C compiler, not a C++ compiler. A C++ compiler may mangle internal names in a manner that is not consistent with the Fortran compiler. This will cause errors during linking. It is suggested that you add these definitions to your *.profile* (or equivalent) startup file.

You may encounter errors either when trying to compile LVT or when trying to run LVT because the compiler or operating system cannot find these libraries. To fix this, you must add these libraries to your *\$LD\_LIBRARY\_PATH* environment variable. For example, say that you are using ESMF, GRIB-API, NetCDF, and HDF5. Then you must execute the following command (written using Bash shell syntax):

```
% export LD_LIBRARY_PATH=$LVT_HDF5/lib:$LVT_LIBESMF:$LVT_NETCDF/lib:$LVT_GRIBAPI/lib:$LD_LIBRARY_PATH
```

It is also suggested that you add this command to your *.profile* (or equivalent) startup file.

5. An example execution of the configure script is shown below:

```
% ./configure
-----
Setting up configuration for LVT version 7.2...
Optimization level (-2=strict checks, -1=debug, 0,1,2,3, default=2):
Assume little/big_endian data format (1-little, 2-big, default=2):
Use NETCDF? (1=yes, 0=no, default=1):
NETCDF version (3 or 4, default=4):
NETCDF use shuffle filter? (1=yes, 0=no, default = 1):
NETCDF use deflate filter? (1=yes, 0=no, default = 1):
NETCDF use deflate level? (1 to 9=yes, 0=no, default = 9):
Use HDF4? (1=yes, 0=no, default=1):
Use HDF5? (1=yes, 0=no, default=1):
Use HDFEOS? (1=yes, 0=no, default=1):
Enable AFWA-specific grib configuration settings? (1=yes, 0=no, default=0):
Enable GeoTIFF support? (1=yes, 0=no, default=1):
Use MATLAB support? (1=yes, 0=no, default=0):
-----
configure.lvt file generated successfully
-----
Settings are written to configure.lvt in the make directory
If you wish to change settings, please edit that file.
To compile, run the compile script.
-----
```

6. Compile the LVT source code by running the *compile* script.

```
% ./compile
This script will compile the libraries provided with LVT, the dependency
generator and then the LVT source code. The executable LVT will be
placed in the $WORKING/src/ directory upon successful completion of
the compile script.
```

7. Finally, copy the *LVT* executable into your running directory, *\$WORKING/run*.

## 5.5 Generating documentation

LVT code uses the ProTex documenting system [2]. The documentation in  $\LaTeX$  format can be produced by using the *doc.csh* in the *\$WORKING/src/utls* directory. This command produces documentation, generating a number of

L<sup>A</sup>T<sub>E</sub>X files. These files can be easily converted to pdf or html formats using utilites such as `pdflatex` or `latex2html`.

## 6 Running the Executable

This section describes how to run the LVT executable.

The single-process version of LVT is executed by the following command issued in the *\$WORKING/run/* directory.

```
% ./LVT <configfile>
```

where *<configfile>* represents the file containing the run time configuration options for LVT. Currently LVT only supports a serial mode.

To customize your run, you must specify a LVT runtime configuration file. See Section 7 for more information.

## 7 LVT config File

This section describes the options in the *lvt.config* file.

### 7.1 Overall driver options

**LVT running mode:** specifies the running mode to be used. Acceptable values are:

Value	Description
“Data intercomparison”	standard analysis mode where a particular data is compared against another
“Benchmarking”	A benchmarking output is generated based on the input training datasets
“DA statistics processing”	data assimilation diagnostics analysis
“DA observation processing”	data assimilation observation analysis
“OPTUE output processing”	parameter estimation/uncertainty output analysis
“RTM output processing”	radiative transfer model output analysis

LVT running mode:	"Data intercomparison"
-------------------	------------------------

**Map projection of the LVT analysis:** specifies the map projection used in the LVT analysis. Acceptable values are:

Value	Description
latlon	Lat/Lon projection with SW to NE data ordering
mercator	Mercator projection with SW to NE data ordering
lambert	Lambert conformal projection with SW to NE data ordering
gaussian	Gaussian domain
polar	Polar stereographic projection with SW to NE data ordering
UTM	UTM domain

Map projection of the LVT analysis:	"latlon"
-------------------------------------	----------

**LVT output format:** specifies the format of the LVT output. Acceptable values are:

Value	Description
binary	Write output in binary format
grib1	Write output in Grib format (not supported yet)
netcdf	Write output in NETCDF format

See Appendix B for more details about the structure of the LVT output files.

LVT output format:	"netcdf"
--------------------	----------

**LVT output methodology:** specifies the output methodology used in LVT. The LVT output is written as a 1-D array containing only land points or as a 2-D array containing both land and water points. 1-d tile space includes the subgrid tiles and ensembles. 1-d grid space includes a vectorized, land-only grid-averaged set of values. Acceptable values are:

Value	Description
"1d tile space"	LVT output in a 1-D tile domain
"2d gridspace"	LVT output in a 2-D grid domain
"1d gridspace"	LVT output in a 1-D grid domain

LVT output methodology:	"2d gridspace"
-------------------------	----------------

**Analysis data sources:** specifies the two sources of data to be used in an LVT comparison. The user must always choose two sources specified in adjacent columns. The second column entry will be taken as the reference data and the first column will be used as the data being evaluated (against the reference data). If the comparison LIS output against a non-LIS data, it is recommended to specify the first source as "LIS output" and then the other data as the second data source.

Acceptable values for each column are:

Value	Description
"none"	template
"LIS output"	output from another LIS run
"LIS DAOBS"	processed observations from a LIS DA run
"ISCCP LST"	ISCCP skin temperature observations
"MODIS LST"	MODIS (Terra/Aqua) land surface temperature observations
"SCAN"	SCAN soil moisture station observations
"NASMD"	North American Soil Moisture Database soil moisture station observations
"ISMN"	ISMN soil moisture station observations
"SURFRAD"	SURFRAD observations
"SNOTEL"	SNOTEL snow water equivalent observations
"LSWG Tb"	Tb brightness temperature observations at the LSWG sites
"FMI SWE"	Finnish Meteorological Institute (FMI) snow course data
"CMC"	Canadian Meteorological Center (CMC) snow depth analysis
"SNODAS"	NOHRSC SNow Data Assimilation (SNODAS) product
"AMSR-E NASA soil moisture"	NASA (NSIDC) retrieval of AMSR-E soil moisture
"AMSR-E LPRM soil moisture"	LPRM (VU) retrieval of AMSR-E soil moisture
"AMMA"	AMMA station observations
"Ameriflux"	Ameriflux station observations
"ARM"	ARM station observations
"SMOSREX"	SMOSREX station observations
"AGRMET"	AGRMET land surface analysis
"Globsnow"	GlobSnow SWE analysis
"SNODEP metobs"	WMO snow depth station observations
"MOD10A1"	MOD10A1 fractional snow cover data from MODIS
"ANSA snowdepth"	ANSA snow depth retrievals
"ANSA SWE"	ANSA SWE retrievals
"CPC precipitation"	CPC unified precipitation product
"USGS streamflow"	USGS streamflow observations
"Naturalized streamflow"	Naturalized streamflow estimates
"FLUXNET"	Gridded FLUXNET data from MPI
"MOD16A2"	MOD16A2 ET products from MODIS
"UW ET"	University of Washington ET products from MODIS
"ALEXI"	ALEXI model ET estimates from USDA
"USDA ARS soil moisture"	soil moisture measurements from USDA ARS watersheds
"GHCN"	Global Historical Climatology Network data
"ALEXI"	Atmosphere Land Exchange Inverse model outputs of ET
"NLDAS2"	North American Land Data Assimilation System Phase-2 data
"GRACE"	processed GRACE data used in a LIS-DA instance
"PBO H2O"	plate boundary observatory data
"USGS ground water well data"	USGS ground water well data
"SMOS L2 soil moisture"	SMOS level 2 soil moisture
"SMOS L1 TB"	SMOS level 1 brightness temperature
"GCOMW AMSR2 L3 soil moisture"	GCOMW AMSR2 level 3 soil moisture
"SMOPS soil moisture"	Soil Moisture Operational Product System data
"ESA CCI soil moisture"	ESA CCI soil moisture



Acceptable values for the 2 character suffix are:

Value	Description
ss	second
mn	minute
hr	hour
da	day
mo	month
yr	year

LVT restart output interval:	"1mo"
------------------------------	-------

LVT restart filename: specifies the name of the LVT restart file

LVT restart filename:	"none"
-----------------------	--------

The start time of the evaluation period is specified in the following format:

Variable	Value	Description
Starting year:	integer 2001 – present	specifying starting year
Starting month:	integer 1 – 12	specifying starting month
Starting day:	integer 1 – 31	specifying starting day
Starting hour:	integer 0 – 23	specifying starting hour
Starting minute:	integer 0 – 59	specifying starting minute
Starting second:	integer 0 – 59	specifying starting second

Starting year:	2007
Starting month:	11
Starting day:	1
Starting hour:	0
Starting minute:	0
Starting second:	0

The end time of the evaluation period is specified in the following format:

Variable	Value	Description
Ending year:	integer 2001 – present	specifying ending year
Ending month:	integer 1 – 12	specifying ending month
Ending day:	integer 1 – 31	specifying ending day
Ending hour:	integer 0 – 23	specifying ending hour
Ending minute:	integer 0 – 59	specifying ending minute
Ending second:	integer 0 – 59	specifying ending second

Ending year:	2008
Ending month:	5
Ending day:	31
Ending hour:	0
Ending minute:	0
Ending second:	0

**LVT clock timestep:** specifies the timestep to be used in the LVT analysis. It is recommended to use a timestep consistent with the output frequency of the first data stream.

LVT clock timestep:	"1da"
---------------------	-------

**Undefined value:** specifies the undefined value. The default is set to -9999.

Undefined value:	-9999
------------------	-------

**LVT diagnostic file:** specifies the name of run time diagnostic file. Acceptable values are any 40 character string.

LVT diagnostic file:	lvtlog
----------------------	--------

## 7.2 Domain specification

LVT expects three sets of domain specification. (1) the domain over which the LVT analysis needs to be carried out (2) the domain in which LIS simulation was carried out (LIS run domain) Section 7.1 lists the projections that LIS supports.

### 7.2.1 LVT run domain

This section describes how to specify the run domain over which LVT will perform its analysis. See the LDT Users' Guide for more details about setting these values.

Run domain lower left lat:	30.125
Run domain lower left lon:	-124.875
Run domain upper right lat:	50.125
Run domain upper right lon:	-69.875
Run domain resolution (dx):	0.25
Run domain resolution (dy):	0.25

**Input domain and mask data file:** specifies the name of the parameter input file to be used for the definition of domain and parameters in LVT. This file should be in NetCDF format and must include details about the map projection (as global attributes) and must include a landmask field. LVT uses the landmask specified in this file to derive the landmask for the LVT run domain. The extents of the run domain should be inclusive of the landmask specified in this file (but it doesn't have to match exactly).

Input domain and mask data file:	./lis_input.d01.nc
----------------------------------	--------------------

**LVT datastream attributes table::** specifies the variables being analyzed and their attributes. The list of variables are to be specified in a table form with each line representing the variable specification from datastream 1 and datastream 2. In the example below, latent heat flux variable from datastream 1 is compared against the sensible heat flux from datastream 2. In addition, the root zone soil moisture from datastream 1 is compared against the root zone soil moisture from datastream 2. Each variable specification consists of 7 columns representing the short name, starting index of the level of the variable (0 indicates that variable is not selected), ending index of the level of the variable, units, direction type, time-averaging option (0 = instantaneous, 1 = time-averaged) and total number of vertical levels. NOTE: This line must end with two colons after the word table (e.g., "table::"), and the final line of the table is a line with only two colons (e.g., "::"). The table information is contained on the lines in-between these beginning and end lines. For example, if the soil moisture variable has 4 levels and the user chooses levels 2 to 3, then they can be entered as (for a datastream.

SoilMoist 2 3 m3/m3 - 1 4

```
LVT datastream attributes table::
Qle      1 1 W/m2  DN  1  1 Qh      1 1 W/m2  DN  1  1
RootMoist 1 1 m3/m3 -  1  1 RootMoist 1 1 m3/m3 -  1  1
::
```

**LVT surface soil layer thickness:** specifies the thickness (in m) of the surface soil layer to be considered in the LVT analysis

```
LVT surface soil layer thickness:      0.1
```

**LVT root zone soil layer thickness:** specifies the thickness (in m) of the root zone soil layer to be considered in the LVT analysis.

```
LVT root zone soil layer thickness:    1.0
```

### 7.3 Analysis options specification

This section of the config file specifies the type of analysis to be conducted during the verification/evaluation. Note that some options are only available in certain running modes.

**Apply external mask:** Specifies whether to apply an external mask in limiting the analysis to a selected set of data points. Note that undefined value is considered to be the value used for omitting grid points. All values other than 'undefined values' (e.g. -9999.0) are considered as valid.

Acceptable values are:

Value	Description
0	Do not apply external mask
1	Apply external, temporally varying mask
2	Apply fixed mask
3	Apply temporal monthly mask

```
Apply external mask:      0
```

**Temporal (monthly) mask flags:** specifies the temporal (monthly) mask flags (specified as 0/1 for each calendar month). This option is only read when the 'Apply external mask' option is set to 3.

Temporal (monthly) mask flags: 0 0 0 0 0 1 1 1 0 0 0 0
--

**External mask directory:** Specifies the name of the data mask file/directory. If the mask varies temporally, then this option specifies the top-level directory containing data mask. Note that the mask files are expected to be in binary, sequential access format.

External mask directory:	"none"
--------------------------	--------

**Compute ensemble metrics:** specifies whether to compute ensemble-based metrics or not. If this option is turned on, then all the traditional (non-ensemble) metrics will be turned off.

Acceptable values are:

Value	Description
0	Do not compute
1	compute ensemble metrics

Compute ensemble metrics:	0
---------------------------	---

**Compute information theory metrics:** specifies whether to compute information theory-based metrics or not. If this option is turned on, then the ensemble and traditional metrics will be turned off.

Acceptable values are:

Value	Description
0	Do not compute
1	compute information theory metrics

Compute information theory metrics:	0
-------------------------------------	---

**Metrics attributes file:** specifies the attributes of the metrics that are used in the LVT analysis. Section 8 describes the format of the metrics attributes file.

Metrics attributes file:	./METRICS.TBL
--------------------------	---------------

**Observation count threshold:** Specifies the number of observations to be used as the minimum threshold for computing statistics. Grid points with observation count less than this value will be ignored.

Acceptable values are 0 or higher

Observation count threshold:	50
------------------------------	----

**Metric computation frequency:** Specifies the temporal averaging interval of the LIS output and observation data.

Note that the ending time and the **Metric computation frequency** must be consistent. For example, for a **Metric computation frequency** of 1da, you must have an ending time of:

Ending hour: 0  
Ending minute: 0  
Ending second: 0

Metric computation frequency:	"1da"
-------------------------------	-------

**Temporal lag in metrics computations:** Specifies the temporal lag in metric computations. The values can be positive or negative (e.g. "+1da" or "-1da")

Temporal lag in metric computations:	0
--------------------------------------	---

**Spatial averaging mode:** Specifies the spatial averaging mode to be used.

Acceptable values are:

Value	Description
pixel-by-pixel	each pixel is treated separately
region-based	stats are computed for on a region by region basis

```
Spatial averaging mode:      "pixel-by-pixel"
```

**Regional mask file for spatial averaging:** Specifies the name of the regional mask file to be used for determining the (sub) regions, if region-based spatial averaging mode is selected.

This file must be in big-endian, sequential access format and must correspond exactly to the LVT run domain.

```
Regional mask file for spatial averaging: none
```

**Metric output directory:** Specifies the top-level directory where the output from the analysis is to be written.

```
Metric output directory:      ./STATS
```

**Metric output frequency:** Specifies the frequency (in seconds) of the analysis output.

Note that the **Metric output frequency** is simply a setting for specifying the frequency of LVT outputs. If the **Metric output frequency** is different from (greater than) the time averaging interval, no additional averaging will be performed between the time averaging intervals.

```
Metric output frequency:      "1da"
```

**Apply temporal smoothing to obs:** specifies whether to temporal smoothing to the observations. If enabled, the code will compute an average value across the specified time window, instead of only using the value that corresponds to the current time.

Acceptable values are:

Value	Description
1	apply temporal smoothing to obs
0	do not apply temporal smoothing to obs

```
Apply temporal smoothing to obs: 0
```

**Obs temporal smoothing window half length:** specifies the observation temporal smoothing window half length. The smoothing window is then defined as (current time +/- half length).

```
Obs temporal smoothing window half length: "2da"
```

**Obs temporal smoothing window interval:** specifies the observation temporal smoothing window interval. This will be used as the increment length across the smoothing window. For e.g., if the window half length is specified as 2 days the smoothing window will be of 5 days. If the smoothing window interval is 1 day, then number of points in the smoothing window will be 5 (-2 da, -1da, current day, +1da, +2da).

```
Obs temporal smoothing window interval: "1da"
```

**Time series location file:** Specifies the name of the file which lists the locations and regions in the domain where ASCII time series data are to be derived. The locations can be specified in three different formats: (1) using the lat/lon values (2) using the column/row indices and (3) using the tile indices. A sample file is shown below:

```
#Number of locations
2
#Location style (1-lat/lon, 2-col/row, 3-tile)
1
#Location name, (next line) SW-lat, SW-lon, NE-lat, NE-lon,
min number of grid points
WEST_US
40 -130 50 -110 5
HIGH_PLAINS_US
43 -110 49 -100 2
```

```
.....  
.....
```

If the location style is 2, the user specifies the column and row indices for the bounding boxes, instead of the corner lat/lon values. A sample file with location style 2 is shown below:

```
#Number of locations  
1  
#Location style (1-lat/lon, 2-col/row, 3-tile)  
2  
#Location name, (next line) SW-col, SW-row, NE-col, NE-row,  
min number of grid points  
WEST_US  
1 1 20 30 5  
EAST_US  
1 1 10 10 5  
.....  
.....
```

If the location style is 3, the user specifies the tile indices for specifying the bounds (starting tile index and ending tile index). A sample file with location style 3 is shown below:

```
#Number of locations  
1  
#Location style (1-lat/lon, 2-col/row, 3-tile)  
3  
#Location name, (next line) Start index, Ending index,  
min number of grid points  
WEST_US  
1 20 5  
EAST_US  
1 10 5  
.....  
.....
```

If the location style is 4, the user explicitly specifies the lat/lons of each grid

point to be used to specify a region. A sample file with location style 4 is shown below:

```
#Number of locations
2
#Location style
4
#number of points followed by lat/lon of each point
REGION1
3
34.4 -103.2
33.4 -100.2
32.1 -99.3
REGION2
2
40.2 -103.3
42.2 -104.2
```

If the location style is 5, the user explicitly specifies a categorical map from which to define subregions. In the map, the categories must be in numerically increasing order from 1. A sample file with location style 5 is shown below:

```
#Number of stations
3
#style
5
#names
NEWENGLAND
1
MIDATLANTIC
1
SOUTHATLANTIC
1
#categorical map
../huc02_conus_0.125dg.1gd4r
```

Please see the sample TS\_LOCATIONS.TXT file for an example in format (1)

Time series location file:	./TS_LOCATIONS.TXT
----------------------------	--------------------

**Variable-based stratification:** Specifies if the errors are to be stratified using one of the model output variables. The errors will be stratified into two levels (1) where the values of the stratification variable falls above the specified threshold and (2) where the values of the stratification variable falls below the specified threshold.

Acceptable values are:

Value	Description
0	Do not stratify
1	Stratify errors

<b>Variable-based stratification:</b>	0
---------------------------------------	---

**Stratification variable:** Specifies the name of the variable to be used in the stratification

<b>Stratification variable:</b>	SWdown_f
---------------------------------	----------

**Stratification threshold:** Specifies the minimum value to be used as the stratification threshold.

<b>Stratification threshold:</b>	1.0
----------------------------------	-----

**Confidence interval (%):** Specifies the confidence interval threshold (in percentage) of the computed statistics

<b>Confidence interval (%):</b>	95
---------------------------------	----

**External data-based stratification:** Specifies if the errors are to be stratified based on an external (static) dataset (e.g. landcover, elevation,etc.) The associated attributes file specifies the stratification details

Acceptable values are:

Value	Description
0	Do not stratify
1	Stratify errors

```
External data-based stratification:      0
```

Stratification attributes file: Specifies the name of the file which lists the details of the stratification. The format of the time series location file is as follows:

```
#Number of stratification data sources
3
#Stratification data files
srtm_elev1km.1gd4r
srtm_slope1km.1gd4r
srtm_aspect1km.1gd4r
#stratification variable name
ELEV
SLOPE
ASPECT
#Max (row 1) min (row2) values for each category
7000 1.0 6
500 0.0 0
#number of bins
12 12 12
```

```
Stratification attributes file:          ./strat_attribs.txt
```

Seasonal cycle interval type: Specifies the interval type for average seasonal cycle computations (when enabled in the METRICS.TBL file)

Acceptable values are:

Value	Description
monthly	monthly seasonal cycles
3 monthly	3-monthly seasonal cycles (DJF,MAM,JJA,SON)
6 monthly	6-monthly seasonal cycles
yearly	yearly seasonal cycles

```
Seasonal cycle interval type:           "monthly"
```

**Seasonal cycle minimum count threshold:** Specifies minimum number of points to be used in computing the average seasonal cycle computations.

Seasonal cycle minimum count threshold:	10
---	----

**Average diurnal cycle minimum count threshold:** Specifies minimum number of points to be used in computing the average diurnal cycle computations.

Average diurnal cycle minimum count threshold:	10
--	----

**Averaging window for computing mean values in anomaly calculations:** Specifies the time window to use for computing mean values to be used in anomaly calculations. This option only applies to the Anomaly metrics (Anomaly, Anomaly R, Anomaly RMSE) Acceptable values are:

Value	Description
monthly	use monthly means
yearly	use annual means

Averaging window for computing mean values in anomaly calculations:	monthly
---	---------

**Compute only the climatology for percentiles:** If set to 1, then LVT will only calculate the climatology when calculating percentiles. After the percentiles have been calculated, then LVT can be run in restart mode using these climatology files without having to calculate the climatology every time. If set to any value other than 1, LVT will first calculate percentiles climatology, and then calculate the percentiles.

Compute only the climatology for percentiles:	0
---	---

**Scale model data prior to computing percentiles:** specifies whether to scale model data prior to computing percentiles. The standard normal deviate based scaling is employed. Acceptable values are:

Value	Description
0	do not scale
1	scale

Percentile scaling mean (input data) filename: specifies the name of the file containing the input data mean.

Percentile scaling standard deviation (input data) filename: specifies the name of the file containing the input data standard deviation.

Percentile scaling mean (scaled data) filename: specifies the name of the file containing the scaled data mean.

Percentile scaling standard deviation (scaled data) filename: specifies the name of the file containing the scaled data standard deviation

Percentile scaling start time for scaling: specifies the time to start scaling.

Percentile scaling end time for scaling: specifies the time to end scaling.

```
Scale model data prior to computing percentiles: 0
Percentile scaling mean (input data) filename:
Percentile scaling standard deviation (input data) filename:
Percentile scaling mean (scaled data) filename:
Percentile scaling standard deviation (scaled data) filename:
Percentile scaling start time for scaling:
Percentile scaling end time for scaling:
```

Compute only the climatology for SGWI: If set to 1, then LVT will only calculate the climatology for SGWI.

```
Compute only the climatology for SGWI:    0
```

Compute only the climatology for SPI: If set to 1, then LVT will only calculate the climatology for SPI.

```
Compute only the climatology for SPI:    0
```

Compute only the climatology for SRI: If set to 1, then LVT will only calculate the climatology for SRI.

Compute only the climatology for SRI: 0

\var{SPI timescale of computation:} Set to 1,3,6,...for SPI (or SRI, SSWI) agregations

Compute only the climatology for SSWI: If set to 1, then LVT will only calculate the climatology for SSWI.

Compute only the climatology for SSWI: 0

Starting month if a shifted year definition is used in temporal averaging: The starting month (integer from 1 to 12) if doing a yearly average or outputting the stats in yearly intervals. Setting this value to 10, for example, represents the start of a hydrologic water year.

Starting month if a shifted year definition is used in temporal averaging: 10

Time specification option for MinTime metric: The 'MinTime' metric computes the time at which the minimum value occurs within the stats writing time window. This particular option specifies the nature of the time value

	Value	Description
	doy	day of year
	mo	month
saved. Acceptable values are:	da	day If doy is chosen, for ex-
	hr	hour
	mn	minute
	ss	second

ample, then the day of the year at which the minimum value occurs will be saved.

Time specification option for Mintime metric: doy

Time specification option for MaxTime metric: The 'Maxtime' metric computes the time at which the maximum value occurs within the stats writing time window. This particular option specifies the nature of the time value

	Value	Description	
	doy	day of year	
	mo	month	
saved. Acceptable values are:	da	day	If doy is chosen, for ex-
	hr	hour	
	mn	minute	
	ss	second	

ample, then the day of the year at which the maximum value occurs will be saved.

Time specification option for MaxTime metric: doy

## 7.4 Data stream sources

This section of the config file specifies the details of the sources of data streams.

### 7.4.1 LIS output

**LIS output analysis data class:** specifies the type of land surface data that is being analyzed. Acceptable values are:

Value	Description
LSM	LSM variables
Routing	Routing variables
RTM	Radiative transfer model variables
Irrigation	Irrigation model output

**LIS output number of surface model types:** specifies the number of surface model types used in the LIS simulation

**LIS output surface model types:** specifies the surface model types used in the LIS simulation, in consecutive columns. Acceptable values are:

Value	Description
LSM	land surface model types
Lake	Lake model types

**LIS output model name:** specifies the name of the model used that generated the output.

Acceptable values are:

Value	Description
“CLSM”	Catchment land surface model
“CLM”	CLM 2.0
“CLSM F2.5”	Catchment Fortuna 2.5
“HYSSIB”	HySSiB
“MOS”	Mosaic
“Noah.2.7.1”	Noah 2.7.1
“Noah.3.2”	Noah 3.2
“Noah.3.3”	Noah 3.3
“SiB2”	SiB2
“TEMPLATE”	template (no model)
“VIC411”	VIC 4.1.1
“WRSI”	GeoWRSI 2.0

**LIS output domain and parameter file:** specifies the name of the parameter input file used in the LIS simulation. This file is generated by the Land Data Toolkit (LDT).

**LIS output directory:** specifies the LIS output directory

**LIS output naming style:** specifies the style of the LIS output. Acceptable values are:

Value	Description
“5 level hierarchy”	5 levels of hierarchy
“3 level hierarchy”	3 levels of hierarchy
“2 level hierarchy”	2 levels of hierarchy
“WMO convention”	WMO convention for weather codes (written by LIS)
“WMO convention (AFW OPS)”	WMO convention for weather codes (for AFW production use)

**LIS output methodology:** specifies the output methodology used for generating the output. The LIS output is written as a 1-D array containing only land points or as a 2-D array containing both land and water points. 1-d tile space includes the subgrid tiles and ensembles. 1-d grid space includes a vectorized, land-only grid-averaged set of values. Acceptable values are:

Value	Description
“1d tilespace”	LIS output in a 1-D tile domain
“2d gridspace”	LIS output in a 2-D grid domain
“1d gridspace”	LIS output in a 1-D grid domain

**LIS output format:** specifies the format of the LIS output. Acceptable values are:

Value	Description
binary	Write output in binary format
grib1	Write output in Grib format (not supported yet)
netcdf	Write output in NETCDF format

**LIS output interval:** specifies the frequency at which the LIS output was written. The time interval is specified with a number followed by a 2 character suffix that indicates the units. For example, an output interval of 1 hour can be specified as “1hr”, “60mn”, or “3600ss”.

Acceptable values for the 2 character suffix are:

Value	Description
ss	second
mn	minute
hr	hour
da	day
mo	month
yr	year

**LIS output attributes file:** specifies the model output attribute file used for generating the LIS output

**LIS output maximum number of surface type tiles per grid:** defines the maximum surface type tiles per grid (this can be as many as the total number of vegetation/landcover types) used in the LIS simulation.

**LIS output minimum cutoff percentage (surface type tiles):** defines the smallest percentage (among the surface type distributions within a grid cell) for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output maximum number of soil texture tiles per grid:** defines the maximum soil texture type tiles per grid (this can be as many as the total number of soil texture types) used in the LIS simulation.

**LIS output minimum cutoff percentage (soil texture tiles):** defines the smallest percentage (among the soil texture distributions within a grid cell) for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output maximum number of soil fraction tiles per grid:** defines the maximum soil fraction tiles per grid used in the LIS simulation.

**LIS output minimum cutoff percentage (soil fraction tiles):** defines the smallest percentage (among the soil fraction distributions within a grid cell)

for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output maximum number of elevation bands per grid:** defines the maximum elevation bands per grid used in the LIS simulation.

**LIS output minimum cutoff percentage (elevation bands):** defines the smallest percentage (among the elevation distributions within a grid cell) for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output maximum number of slope bands per grid:** defines the maximum slope bands per grid used in the LIS simulation.

**LIS output minimum cutoff percentage (slope bands):** defines the smallest percentage (among the slope distributions within a grid cell) for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output maximum number of aspect bands per grid:** defines the maximum aspect bands per grid used in the LIS simulation.

**LIS output minimum cutoff percentage (aspect bands):** defines the smallest percentage (among the aspect distributions within a grid cell) for which to create a tile, used in the LIS simulation. The percentage value is expressed as a fraction.

**LIS output nest index:** specifies the nest index of the domain

**LIS output elevation data source:** specifies the name of the topographical elevation data source used in the LIS run (This information is used to replicate the domain creation that was done in the LIS run).

**LIS output slope data source:** specifies the name of the topographical slope data source used in the LIS run (This information is used to replicate the domain creation that was done in the LIS run).

**LIS output aspect data source:** specifies the name of the topographical aspect data source used in the LIS run (This information is used to replicate the domain creation that was done in the LIS run).

**LIS output soil texture data source:** specifies the name of the soil texture data source used in the LIS run (This information is used to replicate the domain creation that was done in the LIS run).

LIS output soil fraction data source: specifies the name of the soil fraction data source used in the LIS run (This information is used to replicate the domain creation that was done in the LIS run).

LIS output number of soil moisture layers: specifies the number of soil moisture layers used in the LIS output

LIS output number of soil temperature layers: specifies the number of soil temperature layers used in the LIS output

LIS output soil moisture layer thickness: specifies the thicknesses of soil moisture layers in the LIS output

LIS output soil temperature layer thickness: specifies the thicknesses of soil temperature layers in the LIS output

LIS output analysis data class:	"LSM"
LIS output number of surface model types:	1
LIS output surface model types:	"LSM"
LIS output model name:	"Noah.3.3"
LIS output domain and parameter file:	"lis_input.d01.nc"
LIS output directory:	./CLSM/OUTPUT
LIS output naming style:	"3 level hierarchy"
LIS output methodology:	"2d gridspace"
LIS output format:	"netcdf"
LIS output interval:	"1da"
LIS output attributes file:	../Data/Noah33_CONUS/NOAH33_OUTPUT_LIST.TBL
LIS output maximum number of surface type tiles per grid:	1
LIS output minimum cutoff percentage (surface type tiles):	0.10
LIS output maximum number of soil texture tiles per grid:	1
LIS output minimum cutoff percentage (soil texture tiles):	0.10
LIS output maximum number of soil fraction tiles per grid:	1
LIS output minimum cutoff percentage (soil fraction tiles):	0.10
LIS output maximum number of elevation bands per grid:	1
LIS output minimum cutoff percentage (elevation bands):	0.10
LIS output maximum number of slope bands per grid:	1
LIS output minimum cutoff percentage (slope bands):	0.10
LIS output maximum number of aspect bands per grid:	1
LIS output minimum cutoff percentage (aspect bands):	0.10
LIS output number of ensembles per tile:	1
LIS output nest index:	1
LIS output elevation data source:	none
LIS output slope data source:	none
LIS output aspect data source:	none
LIS output soil texture data source:	none

```
LIS output soil fraction data source: none
LIS output number of soil moisture layers: 4
LIS output number of soil temperature layers: 4
LIS output soil moisture layer thickness: 0.1 0.3 0.6 1.0
LIS output soil temperature layer thickness: 0.1 0.3 0.6 1.0
```

#### 7.4.2 AGRMET data

AGRMET data directory: specifies the location of the AGRMET data.

AGRMET data security class name: specifies the security level classification of the data (U for unclassified)

AGRMET data distribution class name: specifies the distribution classification of AGRMET data

AGRMET data category name: specifies category name for AGRMET data.

AGRMET data area of data: specifies geographical extent of AGRMET data

```
AGRMET data directory:                ./AGRMET_data
AGRMET data security class name:      U
AGRMET data distribution class name:  C
AGRMET data category name:           ANLYS
AGRMET data area of data:            GLOBAL
```

#### 7.4.3 ALEXI data

ALEXI data directory: specifies the location of the ALEXI ET data.

ALEXI data resolution (in km): specifies the resolution of the ALEXI ET data in km. Acceptable values are 4 or 10.

```
ALEXI data directory:                ./ALEXI
ALEXI data resolution (in km):      4
```

#### 7.4.4 Ameriflux station observations

**Ameriflux observation directory:** specifies the location of the Ameriflux datasets. Under this directory, the Ameriflux data is expected to be organized by the station names and then under each station name directory, the Level3 Ameriflux files are expected to be staged.

**Ameriflux data level:** specifies the level of Ameriflux data (Note that only level 3 data is currently supported)

**Ameriflux station list file:** specifies the file that lists the location of the Ameriflux stations. The format of the station list is as follows:

```
#nstns
76
#stnname; location name; lat; lon; SWC1 depth; SWC2 depth; TS1 depth; TS2 depth
ARM_SGP_Burn; USARb; 35.5497; -98.0402; 10; 30; 5; 15
ARM_SGP_Control; USARc; 35.5465; -98.0401; 10; 30; 5; 15
ARM_SGP_Main; USARM; 36.6058; -97.4888; 5; 25; 5; 15
Atqasuk; USAtq; 70.4696; -157.4089; -1; -1; 0; 5
Audubon_Grasslands; USAud; 31.5907; -110.5092; 10; 20; 2; 4
Austin_Cary; USSP1; 29.7381; -82.2188; -1; -1; 0; 5
Barrow; USBrw; 71.3225; -156.6259; -1; -1; 0; 5
Bartlett_Experimental_Forest; USBar; 44.0645; -71.2881; 10; -1; 5; -1
Blodgett_Forest; USBlo; 38.8953; -120.6328; 10; 20; 5; 10
Bondville; USBo1; 40.0062; -88.2904; 5; 20; 2; 4
.....
.....
```

Ameriflux observation directory:	./AmeriFlux
Ameriflux data level:	Level3
Ameriflux station list file:	./AmeriFlux/Ameriflux_stns.txt

#### 7.4.5 ANSA snow depth data

**ANSA snow depth observation directory:** specifies the location of the ANSA snow depth observation data (Note that this plugin handles the raw observations that go into the generation of the AFWA ANSA snow depth product)

```
ANSA snow depth observation directory: ./SNODEP
ANSA snow depth lower left lat:      -89.875
ANSA snow depth lower left lon:     -179.875
ANSA snow depth upper right lat:     89.875
ANSA snow depth upper right on:     179.875
ANSA snow depth resolution (dx):     0.25
ANSA snow depth resolution (dy):     0.25
```

#### 7.4.6 ANSA SWE data

**ANSA SWE observation directory:** specifies the location of the ANSA snow water equivalent observation data (Note that this plugin handles the raw observations that go into the generation of the AFWA ANSA snow swe product)

```
ANSA SWE observation directory: ./ANSA_SWE
ANSA SWE lower left lat:         -89.875
ANSA SWE lower left lon:        -179.875
ANSA SWE upper right lat:       89.875
ANSA SWE upper right on:       179.875
ANSA SWE resolution (dx):       0.25
ANSA SWE resolution (dy):       0.25
```

#### 7.4.7 ARM station observations

**ARM observation directory:** specifies the location of the ARM datasets

**ARM site identifier name:** specifies the text identifier (e.g. sgp, twp, nsa, etc.)

**ARM station list file:** specifies the file that lists the location of the ARM stations. The format of the station list is as follows:

**ARM use BAEBBR data:** specifies if to use the BAEBBR data or not

**ARM use EBBR data:** specifies if to use the EBBR data or not

**ARM use ECOR flux data:** specifies if to use the ECOR data or not

**ARM use SWATS data:** specifies if to use the SWATS data or not

ARM use SMOS data: specifies if to use the SMOS data or not

```
#nstns
22
#stnname; lat; lon
E1; 38.202; -99.316
E2; 38.306; -97.301
E3; 38.201; -95.597
E4; 37.953; -98.329
E5; 38.114; -97.513
E6; 37.842; -97.020
E7; 37.383; -96.180
E8; 37.333; -99.309
E9; 37.133; -97.266
.....
.....
```

ARM observation directory:	./ARM_SGP
ARM site identifier name:	sgp
ARM station list file:	./ARM_SGP/sgp_stns.txt
ARM use BAEBBR data:	1
ARM use EBBR data:	1
ARM use ECOR flux data:	1
ARM use SWATS data:	1
ARM use SMOS data:	1

#### 7.4.8 USDA ARS soil moisture observations

ARS soil moisture observation directory: specifies the location of the ARS soil moisture observation data

ARS soil moisture station list file: specifies the file that lists the location of the ARS stations. The format of the file is as follows: ARS station name, station lat, station lon

```
#nstns
4
#stns
wg 31.73 -110.05
```

```
lr 31.50 -83.550
lw 34.95 -97.983
rc 43.07 -116.75
```

```
ARS soil moisture observation directory: ./ARS_Watersheds
ARS soil moisture station list file:    ./ARS_Watersheds/stnlist.dat
```

CMC snow depth observation directory: specifies the location of the CMC snow depth observation data

```
CMC snow depth observation directory:  ./CMC_data
```

#### 7.4.9 SNODAS snow analysis data

SNODAS observation directory: specifies the location of the SNODAS data

```
SNODAS observation directory:         ./SNODAS
```

#### 7.4.10 CPC precipitation data

CPC PCP observation directory: specifies the location of the CPC unified precipitation data

CPC PCP domain type (CONUS or GLOBAL): specifies the version of the CPC unified precipitation data

CPC PCP use real time data: specifies whether to use the real time version of the CPC unified precipitation data

```
CPC PCP observation directory:        ../CPC_CONUS
CPC PCP domain type (CONUS or GLOBAL): CONUS
CPC PCP use real time data:           0
```

#### 7.4.11 ESA CCI soil moisture data

ESA CCI soil moisture data directory: specifies the location of the ESA CCI soil moisture data

ESA CCI soil moisture data version: specifies the version of the ESA CCI data (1 or 2)

```
ESA CCI soil moisture data directory: ../ECV_sm_v2.0/  
ESA CCI soil moisture data version: 2
```

#### 7.4.12 Gridded FLUXNET data

FLUXNET data directory: specifies the location of the gridded FLUXNET data

```
FLUXNET data directory: ./FLUXNET
```

#### 7.4.13 Global Change Observation Mission – Water (GCOMW)

GCOMW AMSR2 L3 soil moisture observation directory: specifies the location of the GCOMW AMSR2 L3 soil moisture observations.

```
GCOMW AMSR2 L3 soil moisture observation directory:
```

#### 7.4.14 Global Historic Climatology Network (GHCN) data

GHCN observation directory: specifies the location of the GHCN data

GHCN station file: specifies the file that lists the GHCN stations in the following format (station id, latitude, longitude, elevation)

```
USC00020170 33.63920 -109.3278 2792.000  
USC00020678 35.23000 -111.8214 2179.900  
USC00020750 36.67780 -110.5411 2220.800
```

USC00021001	36.21470	-112.0620	2438.400
USC00023009	35.16110	-111.7311	2171.700
USC00023828	34.74330	-111.4139	2279.900
USC00025412	34.11420	-109.8589	2237.200
.....			
.....			

GHCN observation directory:	./GHCN
GHCN station file:	./GHCN/ghcnd-qc-stations.txt

#### 7.4.15 GlobSnow data

GlobSnow data directory: specifies the location of the GlobSnow data.

GlobSnow data directory:	./GlobSnow
--------------------------	------------

#### 7.4.16 ISMN soil moisture observations

ISMN observation directory: specifies the location of the ISMN (International Soil Moisture Network) soil moisture observation data

ISMN observation directory:	./ISMN
-----------------------------	--------

#### 7.4.17 LPRM AMSR-E soil moisture retrievals

LPRM AMSR-E soil moisture observation directory: specifies the location of the LPRM AMSR-E soil moisture retrievals

LPRM AMSR-E use raw data: specifies whether to use the LPRM AMSR-E raw data. Acceptable values are:

Value	Description
0	Do not use
1	Use

```
LPRM AMSR-E soil moisture observation directory: ./LPRM-AMSRE
LPRM AMSR-E use raw data: 0
```

#### 7.4.18 MOD16A2 data

MOD16A2 data directory: specifies the location of the MOD16A2 - MODIS based ET data.

```
MOD16A2 data directory: ./MOD16
```

#### 7.4.19 MODIS LST

MODIS LST data directory: specifies the location of the MODIS LST data.

```
MODIS LST data directory:
```

#### 7.4.20 North American Soil Moisture Database (NASMD)

NASMD observation directory: specifies the location of the NASMD observation directory.

NASMD coord file: specifies the name of the NASMD coordinates file.

NASMD number of stations: specifies the number of NASMD stations.

```
NASMD observation directory: ../TAMU_NASMD
NASMD coord file: ../TAMU_NASMD/nasmd_stations.txt
NASMD number of stations: 1289
```

#### 7.4.21 Naturalized monthly streamflow data

Naturalized streamflow observation directory: specifies the location of the naturalized monthly streamflow observation data

**Naturalized streamflow station list file:** lists the locations of the streamflow stations in the following format (total number of stations followed by each usgs station id, latitude, longitude, data coverage begin year, data coverage end year).

```
#nstns
23
#name, lat, lon
ala 31.55 -87.51 1950 1993
apa 29.95 -85.02 1950 1993
del 39.69 -75.69 1948 1987
ftp 48.04 -106.36 1950 2009
gar 47.39 -101.39 1950 2009
gre 40.91 -109.42 1905 2006
.....
.....
```

Naturalized streamflow observation directory: ./Naturalized_StreamFlow
Naturalized streamflow station list file: ./Naturalized_StreamFlow/Naturalized_stnlist.

#### 7.4.22 NLDAS2

**NLDAS2 data directory:** specifies the location of the NLDAS-2 data directory.

**NLDAS2 land surface model:** specifies the NLDAS-2 land-surface model.

**NLDAS2 analysis data class:** specifies the type of NLDAS2 data that is being analyzed. Acceptable values are:

Value	Description
LSM	LSM variables
Routing	Routing variables

**NLDAS2 soil moisture volumetric:** specifies if LVT should convert the NLDAS-2 soil moisture values in amounts (kg m<sup>-2</sup>) to volumetric (m<sup>3</sup> m<sup>-3</sup>), when LVT running mode is set to “Observation processing”. If NLDAS2 soil moisture volumetric is set to “.true”, then the values will be converted.

**NLDAS2 VIC soil depth1 file:** specifies the name of the VIC soil depth 1 binary file.

NLDAS2 VIC soil depth2 file: specifies the name of the VIC soil depth 2 binary file.

NLDAS2 VIC soil depth3 file: specifies the name of the VIC soil depth 3 binary file.

NLDAS2 data directory:	./NLDAS2.VIC
NLDAS2 land surface model:	VIC
NLDAS2 soil moisture volumetric:	.true.
NLDAS2 VIC soil depth1 file:	./vic_depth1.1gd4r
NLDAS2 VIC soil depth2 file:	./vic_depth2.1gd4r
NLDAS2 VIC soil depth3 file:	./vic_depth3.1gd4r

#### 7.4.23 Soil Moisture Operational Processing System (SMOPS)

SMOPS soil moisture observation directory: specifies the location of the SMOPS soil moisture observation directory.

SMOPS soil moisture use ASCAT data: specifies whether to use the ASCAT data. Acceptable values are:

Value	Description
0	do not use
1	use

SMOPS soil moisture use WindSat data: specifies whether to use the WindSat data. Acceptable values are:

Value	Description
0	do not use
1	use

SMOPS soil moisture use SMOS data: specifies whether to use the SMOS data. Acceptable values are:

Value	Description
0	do not use
1	use

SMOPS soil moisture observation directory:	./SMOPS
SMOPS soil moisture use ASCAT data:	1

SMOPS soil moisture use WindSat data:	0
SMOPS soil moisture use SMOS data:	0

#### 7.4.24 SMOS L1 TB

SMOS L1 TB observation directory: specifies the location of the SMOS L1 TB observation directory.

SMOS L1 TB observation directory:
-----------------------------------

#### 7.4.25 SMOS L2 soil moisture

SMOS L2 soil moisture observation directory: specifies the location of the SMOS L2 soil moisture observation directory.

SMOS L2 soil moisture observation directory:
--

#### 7.4.26 SNODEP metobs snow depth data

SNODEP metobs directory: specifies the location of the SNODEP observation data (Note that this plugin handles the raw observations that go into the generation of the AFWA SNODEP product)

SNODEP metobs directory:	./SNODEP
--------------------------	----------

#### 7.4.27 SNOTEL SWE observations

SNOTEL observation directory: specifies the location of the SNOTEL SWE observation data

SNOTEL coord file: specifies the file that lists the location of the SNOTEL stations. The format of the station list is as follows:

AZ	BAKER BUTTE	11R06S	308	34.450	-111.400
AZ	BAKER BUTTE SMT	11R07S	1140	34.450	-111.367
AZ	BALDY	09S01S	310	33.967	-109.500
AZ	BEAVER HEAD	09S06S	902	33.683	-109.200
.....					
.....					

SNOTEL observation directory:	./SNOTEL
SNOTEL coord file:	./SNOTEL/SNOTEL_CONUS_list.txt

#### 7.4.28 SURFRAD observations (radiation, wind speed, pressure)

**SURFRAD observation directory:** specifies the location of the SURFRAD radiation data

SURFRAD observation directory:	./SURFRAD
--------------------------------	-----------

#### 7.4.29 SCAN soil moisture observations

**SCAN observation directory:** specifies the location of the SCAN soil moisture observation data (Note that the plugin handles the “reprocessed” SCAN data from NASA GMAO).

**SCAN number of stations:** specifies the number of SCAN stations used in the analysis

**SCAN coord file:** specifies the file that lists the location of the SCAN stations. The format of the metadata file is as follows: SCAN state, station id, station lat, station lon, elevation

```

AL 2058 34.43 -87 6 633
AR 2030 34.85 -91.88 6 250
AR 2091 34.28 -91.35 6 197
AZ 2026 31.73 -110.05 7 4500
GA 2013 33.88 -83.43 5 770
GA 2027 31.5 -83.55 5 350

```

....  
....

SCAN observation directory:	./SCAN
SCAN number of stations:	37
SCAN coord file:	./SCAN_coord.txt

### 7.4.30 USGS ground water

USGS ground water (well data) observation directory: specifies the location of the USGS ground water (well data) observation directory.

USGS ground water (well data) coord file: specifies the name of the USGS ground water (well data) coordinates file.

USGS ground water (well data) observation directory:	./USGS_GW_welldata
USGS ground water (well data) coord file:	./USGS_GW_welldata/Well_mdata.txt

### 7.4.31 USGS daily streamflow data

USGS streamflow observation directory: specifies the location of the USGS daily streamflow observation data

USGS streamflow station list file: lists the locations of the streamflow stations in the following format (total number of stations followed by each usgs station id, latitude, longitude).

```
#nstns
961
#name, lat, lon
01010000 46.70060 -69.71560
01010500 47.11310 -69.08810
01011000 47.06970 -69.07940
01013500 47.23750 -68.58280
01022500 44.60810 -67.93530
01030500 45.50110 -68.30580
01031500 45.17500 -69.31470
01038000 44.22280 -69.59390
```

```
01047000  44.86920   -69.95500
01052500  44.87750   -71.05750
01054200  44.39060   -70.97970
.....
.....
```

```
USGS streamflow observation directory:  ./USGS_StreamFlow
USGS streamflow station list file:     ./USGS_StreamFlow/USGS_stnlist_nldas.txt
```

#### 7.4.32 University of Washington ET data

UW ET data directory: specifies the location of the UWET ET data.

```
UW ET data directory:                    ./UW_ET_MODIS-SRB_Monthly
```

#### 7.4.33 GIMMS AVHRR NDVI data

GIMMS AVHRR NDVI data directory: specifies the location of the GIMMS NDVI data.

```
GIMMS AVHRR NDVI data directory:        ./GIMMS-3g/
```

#### 7.4.34 GIMMS MODIS NDVI data

GIMMS MODIS NDVI data directory: specifies the location of the GIMMS MODIS NDVI data.

```
GIMMS MODIS NDVI data directory:        ./GIMMS_MODIS_NDVI
```

#### 7.4.35 GLDAS version 2 data

GLDAS2 data directory: specifies the location of the GLDAS2 data.

GLDAS2 data model name: specifies the name of the land surface model used in the GLDAS2 data.

GLDAS2 data directory:	./GLDAS2/
GLDAS2 data model name:	NOAH

#### 7.4.36 MERRA version 2 data

MERRA2 data directory: specifies the location of the MERRA2 data.

MERRA2 data directory:	./MERRA2/
------------------------	-----------

#### 7.4.37 ERA Interim Land data

ERA interim land data directory: specifies the location of the ERA Interim Land data.

ERA interim land data directory:	./ERA_Interim_Land/
----------------------------------	---------------------

#### 7.4.38 SSEB operational data

SSEBop data directory: specifies the location of the SSEB data.

SSEBop process anomaly data: specifies whether to process the ET anomaly data or the raw ET data.

SSEBop data directory:	./SSEB/ETA/
SSEBop process anomaly data:	1

#### 7.4.39 GRDC data

GRDC data directory: specifies the location of the GRDC data.

GRDC station list file: specifies the file that contains the listing of the GRDC stations

GRDC frequency of data: specifies the frequency of the GRDC data (monthly/daily)

```
GRDC data directory:    ../GRDC_data
GRDC station list file: ../GRDC_data/GRDC_stations.txt
GRDC frequency of data: monthly
```

#### 7.4.40 LIS DAOBS output as the observation

LIS DAOBS output directory: specifies the LIS DAOBS output directory

```
LIS DAOBS output directory:    ./DAOBS
```

LIS DAOBS use scaled obs: specifies whether to use scaled obs. Acceptable values are:

Value	Description
0	Do not use scaled obs
1	Use scaled obs

```
LIS DAOBS use scaled obs: 0
```

#### 7.4.41 ISCCP land surface temperature observations

ISCCP Tskin data directory: specifies the location of the ISCCP land surface temperature data

```
ISCCP Tskin data directory:    ./ISCCP
```

#### 7.4.42 LSWG Tb observations

**LSWG Tb observation filename:** specifies the name of the LSWG filename containing Brightness Temperature (Tb) observations

**LSWG Tb satellite name:** specifies the name of satellite – same as what’s used in CRTM

**LSWG Tb data format:** 0 for AMSR-E, 1-for AMSU

**LSWG Tb metadata file:** specifies the file that lists the metadata for LSWG Tb observations. The format of the metadata file is as follows:

```
#nstns, undef, starting time, ending time, timestep (mins)
1 -1 2006 07 01 10 00 2007 06 30 17 00 3600
#LIS channel data index in file
1 1
2 2
3 3
4 4
5 5
6 6
7 7
8 8
9 9
10 10
11 11
12 12
13 13
14 14
15 15
```

**LSWG Tb include cloud masking:** specifies if data is to be ignored in the presence of clouds (0-do not ignore, 1-ignore)

**LSWG Tb cloud mask file:** specifies the name of the cloud mask file

**LSWG Tb cloud mask column:** ??

**LSWG Tb cloud mask threshold(%):** specifies the threshold below which clouds can be ignored (used only if cloud masking is enabled).

LSWG Tb observation filename:	./_LSWG/C3VP.txt
-------------------------------	------------------

LSWG Tb satellite name:	"N18_"
LSWG Tb data format:	1
LSWG Tb metadata file:	./C3VP_mdata
LSWG Tb include cloud masking:	1
LSWG Tb cloud mask file:	./cloud_mask.txt
LSWG Tb cloud mask column:	??
LSWG Tb cloud mask threshold(%):	75

#### 7.4.43 FMI SWE observations

FMISWE observation directory: specifies the location of the FMI snow course data

FMISWE observation directory:	./FMI_SWE
-------------------------------	-----------

#### 7.4.44 CMC daily snow depth observations

#### 7.4.45 NASA AMSR-E soil moisture retrievals

NASA AMSR-E soil moisture observation directory: specifies the location of the standard (NASA) AMSR-E soil moisture retrievals

NASA AMSR-E soil moisture observation directory:	./NASA_AMSRE
--	--------------

#### 7.4.46 AMMA station observations

AMMA observation directory: specifies the location of the AMMA in-situ observations.

AMMA static txt file list: specifies the file with the station file names in text format (.txt)

A sample static txt file list is shown below:

201006140332132535.csv  
201006140337342536.csv  
201006140347082537.csv  
201006140348592538.csv  
201006140351382539.csv  
201006140358582540.csv  
201006140400532541.csv  
201006140402202542.csv  
201006140640302543.csv  
201006140641442544.csv  
201006140642422545.csv  
201006140643372546.csv

AMMA static netcdf file list: specifies the file with the station file names in netcdf format

A sample static txt file list is shown below:

10  
ceh-aws\_agoufou\_20050414.nc  
ceh-aws\_bamba\_20050426.nc  
ceh-aws\_banizoumbou\_20051115.nc  
ceh-aws\_belifoungou\_20051111.nc  
ceh-aws\_bira\_20051113.nc  
ceh-aws\_hedgerit\_20050415.nc  
ceh-aws\_kelema\_20050416.nc  
ceh-aws\_nalohou\_20051111.nc  
ceh-aws\_pobe\_20050220.nc  
ceh-aws\_wankama\_20051117.nc

AMMA soil moisture layer weights: normalized weights to be applied for root zone computations of soil moisture

AMMA soil temperature layer weights: normalized weights to be applied for root zone computations of soil temperature

AMMA observation directory:	./AMMA
AMMA static txt file list:	amma_static_txtfiles.txt
AMMA static netcdf file list:	amma_static_ncfiles.txt

```
AMMA soil moisture layer weights:    0.1875 0.1875 0.625 0.0 0.0
AMMA soil temperature layer weights: 0.1875 0.1875 0.625 0.0 0.0
```

#### 7.4.47 SMOSREX in-situ soil moisture observations

**SMOSREX observation filename:** specifies the name of the SMOSREX observation filename. Currently this plugin only handles a single observation location.

```
SMOSREX observation filename:        ./SMOSREX/Toulouse_SMOSREX.dat
```

#### 7.4.48 MOD10A1 snow cover data

**MOD10A1 observation directory:** specifies the location of the 1km resolution MOD10A1 fractional snow cover data

```
MOD10A1 observation directory:       ./MOD10A1
```

#### 7.4.49 GRACE (processed from LDT) data

**GRACE data directory:** specifies the location of the GRACE data (note that this plugin handles the “processed” GRACE data, where the GRACE TWS anomalies have been added to the LIS model TWS).

**GRACE configuration:** specifies the GRACE configuration. Acceptable values are:

Value	Description
default	GRACE
follow-on	GRACE follow-on
GRACE-2	GRACE 2

```
GRACE data directory:  ./GRACE
GRACE configuration:   default
```

#### 7.4.50 CEOP

CEOP data directory: specifies the location of the CEOP data.

CEOP station list file: specifies the location of the CEOP station list file.

CEOP read surface meteorology data: specifies whether to read the CEOP surface meteorology data. Acceptable values are:

Value	Description
0	do not read
1	read

CEOP read flux data: specifies whether to read the CEOP flux data. Acceptable values are:

Value	Description
0	do not read
1	read

CEOP read soil moisture and temperature data: specifies whether to read the CEOP soil moisture and temperature data. Acceptable values are:

Value	Description
0	do not read
1	read

CEOP data directory:	./CEOP
CEOP station list file:	
CEOP read surface meteorology data:	1
CEOP read flux data:	1
CEOP read soil moisture and temperature data:	1

#### 7.4.51 COOP

COOP data directory: specifies the location of the COOP data.

COOP coord file: specifies the name of the COOP coordinates file.

COOP metadata file: specifies the name of the COOP metadata file.

COOP data directory:	
----------------------	--

COOP coord file:  
COOP metadata file:

#### 7.4.52 Great Lakes Environmental Research Lab (GLERL)

GLERL hydro data directory: specifies the location of the GLERL hydro data.

GLERL hydro lake locations file: specifies the name of the GLERL hydro lake locations file.

GLERL hydro data directory:  
GLERL hydro lake locations file:

#### 7.4.53 GSOD

GSOD observation directory: specifies the location of the GSOD observation data.

GSOD coord file: specifies the name of the GSOD coordinates file.

GSOD metadata file: specifies the name of the GSOD metadata file.

GSOD observation directory:  
GSOD coord file:  
GSOD metadata file:

#### 7.4.54 Plate Boundary Observatory H2O (PBOH2O)

PBOH2O observation directory: specifies the location of the PBOH2O observation directory.

PBOH2O station list file: specifies the name of the PBOH2O station list file.

PBOH2O observation directory:  
PBOH2O station list file:

#### 7.4.55 WG PBMR

WG PBMR observation directory: specifies the location of the WG PBMR observation directory.

WG PBMR site index: specifies the location of the WG PBMR site index.

```
WG PBMR observation directory:  
WG PBMR site index:
```

#### 7.4.56 GLEAM

GLEAM data directory: specifies the location of the GLEAM data directory.

GLEAM data version: specifies the version of the GLEAM data

Acceptable values are:

Value	Description
3.0a	version 3.0a
3.0b	version 3.0b
3.0c	version 3.0c

```
GLEAM data directory:      ./GLEAM/  
GLEAM data version:      '3.0a'
```

#### 7.4.57 FLUXNET2015

FLUXNET2015 observation directory: specifies the location of the FLUXNET2015 data

FLUXNET2015 station list file: specifies the list of stations in the FLUXNET2015 data.

```
FLUXNET2015 observation directory: ./FLUXNET2015_STN/  
FLUXNET2015 station list file:    ./FLUXNET2015_STN/STN_list.dat
```

#### 7.4.58 USCRN soil moisture

USCRN soil moisture observation directory: specifies the location of the USCRN soil moisture data

USCRN soil moisture station file: specifies the list of stations in the USCRN data.

USCRN soil moisture observation directory:	./USCRN
USCRN soil moisture station file:	./USCRN/USCRN_stations.txt

#### 7.4.59 WG SWRC

WG SWRC observation directory: specifies the location of the WG SWRC observation directory.

WG SWRC station list file: specifies the name of the WG SWRC station list file.

WG SWRC observation directory:	
WG SWRC station list file:	

### 7.5 OptUE processing options

This section of the config file specifies the details of the optimization and uncertainty estimation processing options, and the specialized options to analyze outputs from the Optimization/Uncertainty Estimation algorithms.

LIS OptUE restart file: the name of the file that specifies the parameter distributions LVT expects this information to be provided through the uncertainty estimation algorithm restart file. Note that this option needs to be specified only if ensemble cross correlation metric is enabled.

LIS OptUE restart file:	MCSIM.001.MCSIMrst
-------------------------	--------------------

LIS OptUE number of model parameters: specifies the number of model parameters in the uncertainty estimation algorithm restart file. Note that this option needs to be specified only if ensemble cross correlation metric is enabled.

LIS OptUE number of model parameters: 4

OptUE algorithm used: specifies the index of the optimization/uncertainty estimation algorithm used

Acceptable values are:

Value	Description
1	Levenberg- Marquardt
2	Genetic Algorithm
3	SCE-UA
4	MCSIM
5	MCMC
6	DEMC

OptUE algorithm used: 2

OptUE decision space attributes file: lists the decision space attributes file used in the LIS optimization/uncertainty estimation integration.

OptUE decision space attributes file: ./GARun/noah\_sm\_decspace.txt

OptUE number of iterations: Number of generations used in the optimization/uncertainty estimation algorithm.

OptUE number of iterations: 20

OptUE compute time series: specifies if a time series of OptUE run output data is to be generated (0-no, 1-yes)

OptUE compute time series: 1

OptUE time series location file: specifies the file which lists the locations in the domain where the time series data are to be extracted. The format of the time series location file is as follows:

```

#Number of locations
1
#Location style (1-lat/lon, 2-col/row, 3-tile)
2
#mask filename
none
#site name
Site1
244 236

```

OptUE time series location file:	./STN_LOCATIONS.DAT
----------------------------------	---------------------

OptUE total number of parameters: specifies the total number of parameters.

OptUE total number of parameters:	2
-----------------------------------	---

OptUE total number of selected parameters: specifies the total number of selected parameters.

OptUE total number of selected parameters:	1
--	---

## 7.6 DA diagnostics analysis

This section of the config file specifies the specialized options to analyze the data assimilation diagnostics. These options are employed for runmode="DA statistics processing"

**Compute innovation distribution:** Specifies if innovation distribution analysis (computing mean and variance) is to be computed.

Acceptable values are:

Value	Description
0	Do not compute
1	Compute

`Compute analysis gain`: specifies if analysis gain is to be computed.

Acceptable values are:

Value	Description
0	Do not compute
1	Compute

`Number of state variables in the DA update` specifies the number of state variables in the DA update.

<code>Compute Innovation Distribution:</code>	1
<code>Compute analysis gain:</code>	0
<code>Number of state variables in the DA update:</code>	4

## 7.7 DA observation analysis

This runmode is used to conduct analysis of observations used in the DA assimilation instance. LIS DA subsystem generates processed (interpolated, QC'd) estimates of input observations. This runmode enables analysis of such data.

No specialized options are necessary, except specifying the 'LIS output attributes file:' option to correspond to the DA output. For example, if the DA instance generates estimates of a single variable (say SWE) then specify the LIS output attributes file such that (only) SWE is present in the (LIS) output file. In other words, column number 2 should indicate 1 for SWE variable and 0 for every other variable. If multiple observation types are present in the DA output, then column number 2 should be appropriately modified.

## 8 Configuration of metrics

This section defines the specification of various metrics in LVT. This file is specified in a space delimited column format. Each row consists of the following entries:

**Name:** Name of the metric

**Use option:** determines whether to use this metric. When enabled, the metric will be computed through the duration of the evaluation and a final file will be written out. Acceptable values are:

Value	Description
0	do not use the metric
1	use the metric

**Time option:** specifies whether to compute the metric in time, at the specified stats output intervals. Acceptable values are:

Value	Description
0	do not compute the metric
1	compute the metric

**Temporal output:** determines whether to write (gridded) metric files at the specified stats output intervals. The 'Time option' must also be enabled when this option is enabled. Acceptable values are:

Value	Description
0	Do no write
1	write

**Extract time series:** determines whether to extract (ASCII) time series files for the metric, at each sub-domains specified in the time series location file. Acceptable values are:

Value	Description
0	Do no write
1	write

**Threshold:** The threshold value to be used in computing the metric. Note that

this is used only for the categorical metrics.

**Compute average seasonal cycle:** determines whether to generate the average seasonal cycle of the metric (for each domain specified in the time series location file). Acceptable values are:

Value	Description
0	Do no generate
1	generate

**Compute average diurnal cycle:** determines whether to generate the average diurnal cycle of the metric (for each domain specified in the time series location file). Acceptable values are:

Value	Description
0	Do no generate
1	generate

#name	total	in-time	writeTS	extractTS	threshold	ASC	ADC	
Mean:	1	1	0	1	-9999.0	0	0	#Mean
Min:	0	0	0	0	-9999.0	0	0	#Minimum
MinTime:	0	0	0	0	-9999.0	0	0	#MinTime
Max:	0	0	0	0	-9999.0	0	0	#Maximum
MaxTime:	0	0	0	0	-9999.0	0	0	#MaxTime
Sum:	0	0	0	0	-9999.0	0	0	#Sum
Anomaly:	0	0	0	0	-9999.0	0	0	#Anomaly
Standard deviation:	0	0	0	0	-9999.0	0	0	#Std
RMSE:	0	0	0	0	-9999.0	0	0	#RMSE
Bias:	0	0	0	0	-9999.0	0	0	#Bias
ubRMSE:	0	0	0	0	-9999.0	0	0	#ubRMSE
Mean absolute error:	0	0	0	0	-9999.0	0	0	#MAE
Anomaly RMSE:	0	0	0	0	-9999.0	0	0	#ARMSE
Anomaly correlation:	0	0	0	0	-9999.0	0	0	#ARMSE
Raw correlation:	0	0	0	0	-9999.0	0	0	#RCORR
Rank correlation:	0	0	0	0	-9999.0	0	0	#RnkCORR
Probability of detection (PODy):	0	0	0	0	0.1	0	0	#PODy
Probability of detection (PODn):	0	0	0	0	0.1	0	0	#PODn
False alarm ratio (FAR):	0	0	0	0	0.1	0	0	#FAR
Probability of false detection (POFD):	0	0	0	0	0.1	0	0	#POFD
Critical success index (CSI):	0	0	0	0	0.1	0	0	#CSI
Accuracy measure (ACC):	0	0	0	0	0.1	0	0	#ACC
Frequency bias (FBIAS):	0	0	0	0	0.1	0	0	#FBIAS
Equitable threat score (ETS):	0	0	0	0	0.1	0	0	#ETS
Area metric:	0	0	0	0	-9999.0	0	0	#Area
Nash sutcliffe efficiency:	0	0	0	0	-9999.0	0	0	#NSE

Ensemble mean:	1	1	0	1	-9999.0	0	0	#ensmean
Ensemble standard deviation:	1	1	0	1	-9999.0	0	0	#ensstd
Ensemble likelihood:	1	1	0	1	-9999.0	0	0	#ensll
Ensemble cross correlation:	1	1	0	1	-9999.0	0	0	#ensxcorr
Ensemble skill:	0	0	0	0	-9999.0	0	0	#ensskill
Ensemble mean error:	0	0	0	0	-9999.0	0	0	#ensmerror
Ensemble mean bias:	0	0	0	0	-9999.0	0	0	#ensmbias
Ensemble spread:	0	0	0	0	-9999.0	0	0	#ensspread
Metric entropy:	0	0	0	0	-9999.0	0	0	#mentropy
Information gain:	0	0	0	0	-9999.0	0	0	#igain
Fluctuation complexity:	0	0	0	0	-9999.0	0	0	#fcomplexity
Effective complexity:	0	0	0	0	-9999.0	0	0	#ecomplexity
Wavelet stat:	0	0	0	0	-9999.0	0	0	#waveletstat
Hausdorff norm:	0	0	0	0	-9999.0	0	0	#Hnorm
Standard precipitation index:	0	0	0	0	-9999.0	0	0	#SPI
Standard runoff index:	0	0	0	0	-9999.0	0	0	#SRI
Standardized soil water index:	0	0	0	0	-9999.0	0	0	#SSWI
Standardized ground water index:	0	0	0	0	-9999.0	0	0	#SGWI
Percentile:	0	0	0	0	-9999.0	0	0	#Percentile
River flow variate:	0	0	0	0	-9999.0	0	0	#RFV
K-S test:	0	0	0	0	-9999.0	0	0	#K-S test
Tendency:	0	0	0	0	-9999.0	0	0	#Tendency
Tendency correlation:	0	0	0	0	-9999.0	0	0	#Tendency correlation

## 9 Model Output Specifications

This section defines the specification of the model output from LIS. This file is specified in a space delimited column format. Each row consists of the following entries:

**Short Name** ALMA compliant short name of the variable.

**Use option** determines whether to write the variable. Acceptable values are:

Value	Description
0	do not write the variable
1	write the variable

**Units** the desired unit of the output variable.

**Sign Convention** direction in which the variable is considered to have positive values. Note that the land models in LIS employ the “traditional approach” where all variables are considered positive in their dominant direction. i.e. precipitation and radiation are positive towards the surface (downward), evaporation, sensible heat and runoff are positive away from the surface. Acceptable values are:

Value	Description
-	No sign
UP DN	Up or Down (Used for fluxes, Precip)
IN OUT	In or Out of the grid cell (Used for runoff, baseflow)
INC DEC	Increase or Decrease (Used for change in storager terms)
S2L L2S	Solid to Liquid and Liquid to Solid (for phase change terms)
S2V V2S	Solid to Vapor and Vapor to Solid (for phase change terms)
E N	Eastward and Northward (used for Wind components)

**Time Average option** determines how temporally process the variable. Acceptable values are:

Value	Description
0	Instantaneous output
1	Time averaged output
2	Instantaneous and Time averaged output
3	Accumulated output

**Min/Max option** determines whether to record minimum and maximum values for the variable. For a given grid-cell, the minimum and maximum values correspond to the minimum and maximum found for all subgrid tiles and ensembles contained in the grid-cell during that output interval. Acceptable values are:

Value	Description
0	Do not compute minimum and maximum values
1	Do compute minimum and maximum values

**Standard Deviation option** determines whether to record the standard deviation of the values for the variable. For a given grid-cell, the standard deviation is a measure of the spread of the subgrid tiles and ensembles contained within the grid-cell from the grid-cell's mean. Acceptable values are:

Value	Description
0	Do not compute standard deviation
1	Do compute standard deviation

**Number of vertical levels** The number of vertical levels corresponding to the variable.

**grib ID** The grib ID to be used for the variable if output is written in grib1 format.

**grib scale factor** The grib scale factor to be used for the variable if output is written in grib1 format.

**Use in LVT option** determines whether to include the variable in the LVT analysis. Acceptable values are:

Value	Description
0	Do not include the variable
1	Do include the variable
<i>n</i>	Enable the variable for analysis and include additional ( <i>n</i> ) layers

Note that this is a full list of output variables. Not all models support all these variables. You must check the source code to verify that the model you want to run supports the variables that you want to write.

```
#short_name select? units signconv timeavg? min/max? std? vert.levels grib_id grib_scalefactor LVT? longname

#Energy balance components
Swnet:      0 W/m2   DN   1 0 0 1 111 10   0 # Net shortwave radiation (W/m2)
Lwnet:      0 W/m2   DN   1 0 0 1 112 10   0 # Net longwave radiation (W/m2)
Q1e:        1 W/m2   UP   1 0 0 1 121 10   1 # Latent heat flux (W/m2)
Qh:         1 W/m2   UP   1 0 0 1 122 10   1 # Sensible heat flux (W/m2)
Qg:         1 W/m2   DN   1 0 0 1 155 10   1 # Ground heat flux (W/m2)
Qf:         0 W/m2   S2L  1 0 0 1 229 10   0 # Energy of fusion (W/m2)
Qv:         0 W/m2   S2V  1 0 0 1 198 10   0 # Energy of sublimation (W/m2)
Qa:         0 W/m2   DN   1 0 0 1 136 10   0 # Advective energy (W/m2)
Qtau:       0 N/m2   DN   1 0 0 1 172 10   0 # Momentum flux (N/m2)
DelSurfHeat: 0 J/m2   INC  1 0 0 1 137 10   0 # Change in surface heat storage (J/m2)
DelColdCont: 0 J/m2   INC  1 0 0 1 138 10   0 # Change in snow cold content (J/m2)
BR:         0 -      -    1 0 1 1 256 10   0 # Bowen ratio
```

```

EF:          0 - - 1 0 1 1 256 10 0 # Evaporative fraction

#Water balance components
Snowf:      0 kg/m2s DN 1 0 0 1 161 10000 0 # Snowfall rate (kg/m2s)
Rainf:      0 kg/m2s DN 1 0 0 1 162 10000 0 # Rainfall rate (kg/m2s)
RainfConv:  0 kg/m2s DN 1 0 0 1 63 10000 0 # Convective rainfall rate (kg/m2s)
TotalPrecip: 1 kg/m2s DN 1 0 0 1 61 10000 0 # Total precipitation rate (kg/m2s)
Evap:       0 kg/m2s UP 1 0 0 1 57 10000 0 # Total evapotranspiration (kg/m2s)
Qs:         0 kg/m2s OUT 1 0 0 1 235 10000 0 # Surface runoff (kg/m2s)
Qrec:       0 kg/m2s IN 1 0 0 1 163 10000 0 # Recharge (kg/m2s)
Qsb:        0 kg/m2s OUT 1 0 0 1 234 10000 0 # Subsurface runoff (kg/m2s)
Qsm:        0 kg/m2s S2L 1 0 0 1 99 10000 0 # Snowmelt (kg/m2s)
Qfz:        0 kg/m2s L2S 1 0 0 1 130 10000 0 # Refreezing of water in the snowpack (kg/m2s)
Qst:        0 kg/m2s - 1 0 0 1 131 10000 0 # Snow throughfall (kg/m2s)
DelSoilMoist: 0 kg/m2 INC 1 0 0 1 132 10000 0 # Change in soil moisture (kg/m2)
DelSWE:     0 kg/m2 INC 1 0 0 1 133 1000 0 # Change in snow water equivalent (kg/m2)
DelSurfStor: 0 kg/m2 INC 1 0 0 1 134 1000 0 # Change in surface water storage (kg/m2)
DelIntercept: 0 kg/m2 INC 1 0 0 1 135 1000 0 # Change in interception storage (kg/m2)
RHMin:      0 - - 1 0 0 1 52 10 0 # Minimum 2-meter relative humidity (-)
Ch:         0 - - 1 0 0 1 208 10 0 # Surface exchange coefficient for heat
Cm:         0 - - 1 0 0 1 252 10 0 # Surface exchange coefficient for momentum
MixRatio:   0 kg/kg - 1 0 0 1 53 10 0 # Mixing ratio

#Surface state variables
SnowT:      0 K - 1 0 0 1 165 10 0 # Snow surface temperature (K)
VegT:       0 K - 1 0 0 1 146 10 0 # Vegetation canopy temperature (K)
BareSoilT:  0 K - 1 0 0 1 147 10 0 # Temperature of bare soil (K)
AvgSurfT:   0 K - 1 0 0 1 148 10 0 # Average surface temperature (K)
RadT:       0 K - 1 0 0 1 149 10 0 # Surface radiative temperature (K)
Albedo:     0 - - 0 0 0 1 84 100 0 # Surface albedo (-)
SWE:        0 kg/m2 - 0 0 0 1 65 1000 0 # Snow Water Equivalent (kg/m2)
SWEVeg:     0 kg/m2 - 1 0 0 1 139 1000 0 # SWE intercepted by vegetation (kg/m2)
SurfStor:   0 kg/m2 - 1 0 0 1 150 1000 0 # Surface water storage (kg/m2)

#Subsurface state variables
SoilMoist:  1 kg/m2 - 0 0 0 4 86 1000 0 # Average layer soil moisture (kg/m2)
SoilTemp:   1 K - 0 0 0 4 85 1000 0 # Average layer soil temperature (K)
SmLiqFrac:  0 - - 0 0 0 4 160 100 0 # Average layer fraction of liquid moisture (-)
SmFrozFrac: 0 - - 0 0 0 4 140 100 0 # Average layer fraction of frozen moisture (-)
SoilWet:    0 - - 0 0 0 1 144 100 0 # Total soil wetness (-)
RelSMC:     0 m3/m3 - 0 0 0 4 141 1000 0 # Relative soil moisture
RootTemp:   0 K - 0 0 0 1 142 1000 0 # Rootzone temperature (K)

#Evaporation components
PotEvap:    0 kg/m2s UP 1 0 0 1 145 1 0 # Potential evapotranspiration (kg/m2s)
ECanop:     0 kg/m2s UP 1 0 0 1 200 1 0 # Interception evaporation (kg/m2s)
TVeg:       0 kg/m2s UP 1 0 0 1 210 1 0 # Vegetation transpiration (kg/m2s)
ESoil:      0 kg/m2s UP 1 0 0 1 199 1 0 # Bare soil evaporation (kg/m2s)
EWater:     0 kg/m2s UP 1 0 0 1 197 1 0 # Open water evaporation (kg/m2s)
RootMoist:  0 kg/m2 - 0 0 0 1 171 1 0 # Root zone soil moisture (kg/m2)
CanopInt:   0 kg/m2 - 0 0 0 1 223 1000 0 # Total canopy water storage (kg/m2)
EvapSnow:   0 kg/m2s - 1 0 0 1 173 1000 0 # Snow evaporation (kg/m2s)
SubSnow:    0 kg/m2s - 1 0 0 1 198 1000 0 # Snow sublimation (kg/m2s)
SubSurf:    0 kg/m2s - 1 0 0 1 143 1000 0 # Sublimation of the snow free area (kg/m2s)
ACond:      0 m/s - 1 0 0 1 179 100000 0 # Aerodynamic conductance
CCond:      0 m/s - 1 0 0 1 181 100000 0 # Canopy conductance

```

```

#Other hydrologic variables
WaterTableD: 0 m - 0 0 0 1 174 1 0 # Water table depth (m)
TWS: 0 mm - 0 0 0 1 175 1 0 # Terrestrial water storage (mm)
GWS: 0 mm - 1 0 0 1 176 1 0 # Ground Water Storage (mm)
WT: 0 mm - 1 0 0 1 177 1 0 # Noah-MP WT variable (mm)

#Cold season processes
Snowcover: 0 - - 0 0 0 1 238 100 0 # Snow cover (-)
SAlbedo: 0 - - 0 0 0 1 184 1000 0 # Albedo of the snow-covered area (-)
SnowTProf: 0 K - 0 0 0 1 239 1000 0 # Temperature of the snow pack (K)
SnowDepth: 0 m - 0 0 0 1 66 1000 0 # Snow depth (m)
SLiqFrac: 0 - - 0 0 0 1 185 1000 0 # Fraction of SWE in the liquid phase

#Variables to compared against remote sensed data
LWup: 0 W/m2 UP 1 0 0 1 212 1 0 # Longwave radiation up from the surface (W/m2)

#Carbon variables
GPP: 0 kg/m2s2 DN 1 0 0 1 256 1 0 # Gross Primary Production
NPP: 0 kg/m2s2 DN 1 0 0 1 256 1 0 # Net Primary Production
NEE: 0 kg/m2s2 UP 1 0 0 1 256 1 0 # Net Ecosystem Exchange
AutoResp: 0 kg/m2s2 UP 1 0 0 1 256 1 0 # Autotrophic respiration
HeteroResp: 0 kg/m2s2 UP 1 0 0 1 256 1 0 # Heterotrophic respiration
LeafResp: 0 kg/m2s2 UP 1 0 0 1 256 1 0 # Leaf respiration
TotSoilCarb: 0 kg/m2 - 1 0 0 1 256 1 0 # Total soil carbon
TotLivBiom: 0 kg/m2 - 1 0 0 1 256 1 0 # Total living biomass

#Forcings
Wind_f: 1 m/s - 1 0 0 1 32 10 0 # Near surface wind (m/s)
Rainf_f: 0 kg/m2s DN 1 0 0 1 162 1000 0 # Average rainfall rate
Snowf_f: 0 kg/m2s DN 1 0 0 1 161 1000 0 # Average snowfall rate
Tair_f: 1 K - 1 0 0 1 11 10 0 # Near surface air temperature
Qair_f: 1 kg/kg - 1 0 0 1 51 1000 0 # Near surface specific humidity
Psurf_f: 1 Pa - 1 0 0 1 1 10 0 # Surface pressure
SWdown_f: 1 W/m2 DN 1 0 0 1 204 10 0 # Surface incident shortwave radiation
LWdown_f: 1 W/m2 DN 1 0 0 1 205 10 0 # Surface incident longwave radiation
PARDR_f: 0 W/m2 DN 1 0 0 1 256 10 0 # Surface incident PAR direct
PARDF_f: 0 W/m2 DN 1 0 0 1 256 10 0 # Surface incident PAR diffuse

#Additional forcings
DirectSW_f: 0 W/m2 - 1 0 0 1 166 10 0 # Surface direct incident shortwave radiation
DiffuseSW_f: 0 W/m2 - 1 0 0 1 167 10 0 # Surface diffuse incident shortwave radiation
NWind_f: 0 m/s N 1 0 0 1 34 10 0 # Northward wind
EWind_f: 0 m/s E 1 0 0 1 33 10 0 # Eastward wind
FHeight_f: 0 m - 1 0 0 1 256 10 0 # Height of forcing variables
CH_f: 0 - - 1 0 0 1 208 10 0 # Surface exchange coefficient for heat
CM_f: 0 - - 1 0 0 1 252 10 0 # Surface exchange coefficient for momentum
Emiss_f: 0 - - 1 0 0 1 256 10 0 # Surface emissivity
MixRatio_f: 0 kg/kg - 1 0 0 1 53 10 0 # Surface mixing ratio
CosZenith_f: 0 - - 1 0 0 1 256 10 0 # Cosine of zenith angle
Albedo_f: 0 - - 1 0 0 1 84 10 0 # Surface albedo

#Parameters
Landmask: 0 - - 0 0 0 1 81 1 0 # Land mask (0 - Water, 1 - Land)
Landcover: 0 - - 0 0 0 1 225 1 0 # Land cover
Soiltype: 0 - - 0 0 0 1 224 1 0 # Soil type
SandFrac: 0 - - 0 0 0 1 256 1 0 # Sand fraction
ClayFrac: 0 - - 0 0 0 1 256 1 0 # Clay fraction

```

SiltFrac:	0	-	-	0	0	0	1	256	1	0	# Silt fraction
Porosity:	0	-	-	0	0	0	1	240	1	0	# Porosity
Soilcolor:	0	-	-	0	0	0	1	256	1	0	# Soil color
Elevation:	0	m	-	0	0	0	1	196	10	0	# Elevation
Slope:	0	-	-	0	0	0	1	222	10	0	# Slope
LAI:	0	-	-	0	0	0	1	182	100	0	# LAI
SAI:	0	-	-	0	0	0	1	256	100	0	# SAI
Snfralbedo:	0	-	-	0	0	0	1	184	100	0	# Snow fraction albedo
Mxsnalbedo:	0	-	-	0	0	0	1	159	100	0	# Maximum snow albedo
Greenness:	0	-	-	0	0	0	1	87	100	0	# Greenness
Roughness:	0	m	-	1	0	0	1	83	10	0	# Roughness
Tempbot:	0	-	-	0	0	0	1	256	10	0	# Bottom soil temperature
#Routing											
Streamflow:	0	m3/s	-	0	0	0	1	256	10	0	# Streamflow
#Noah-MP											
LeafMass:	0	g/m2	-	1	0	0	1	148	10		# leaf mass
RootMass:	0	g/m2	-	1	0	0	1	148	10		# stem mass
StemMass:	0	g/m2	-	1	0	0	1	148	10		# wood mass
WoodMass:	0	g/m2	-	1	0	0	1	148	10		# mass of wood including woody roots [g/m2]
DeepSoilCarbon:	0	g/m2	-	1	0	0	1	148	10		# stable carbon in deep soil [g/m2]
ShallowSoilCarbon:	0	g/m2	-	1	0	0	1	148	10		# short-lived carbon in shallow soil [g/m2]
#LVT combination variables											
EBAL:	0	-	-	1	0	0	1	256	10	0	# Energy balance
WBAL:	0	-	-	1	0	0	1	256	10	0	# Water balance
EVAPBAL:	0	-	-	1	0	0	1	256	10	0	# Evaporation balance
SWE/P:	0	-	-	1	0	0	1	256	10	0	# SWE over precipitation
ET/P:	0	-	-	1	0	0	1	256	10	0	# Evapotranspiration over precipitation
Qs/P:	0	-	-	1	0	0	1	256	10	0	# Surface runoff over precipitation
Qsb/P:	0	-	-	1	0	0	1	256	10	0	# Subsurface runoff over precipitation

## A How to verify a “non-LIS” dataset?

This section provides a description of how to convert a non-LIS data to a “LIS-style” so that verification and evaluation can be conducted using LVT.

First, an observation plugin for the dataset of interest must be developed within LVT. This plugin will handle the reading, processing and any spatial interpolation of the data and will connect the processed variables to the LVT core using the `LVT_logSingleVar` interface.

In the `lvt.config` file, specify the runmode to be “Observation processing”.

```
LIS Running mode: "Observation processing"
```

Though not used, the files `METRICS.TBL`, `TS_LOCATIONS.TXT` must be provided as a placeholder. The sample files provided along with the source code (under `src/configs`) can be used.

Finally, specify the `MODEL_OUTPUT_LIST_LVT.TBL` file such that the selection option for all the variables that should appear in the reprocessed files is enabled (Note that this is the second column in the file `MODEL_OUTPUT_LIST_LVT.TBL`. The last column which specifies “Use in LVT” option is ignored in this running mode.

The processed files in the “LIS-style” will be generated in the location specified by the following option:

```
Stats output directory: ./OUTPUT
```

## B Description of output files from LVT

This section provides a description of various output files generated during an LVT analysis.

For the purposes of illustration, consider the following parameters for an LVT analysis

- Variables :  $Q_{le}$ ,  $Q_h$
- Metrics : *MEAN* and *RMSE*
- LSM : *Noah 3.2*
- location (from *TS\_LOCATIONS.TXT*) : *E20*
- Experiment name : *RUN*

### B.0.1 METADATA files

If the LVT output format is specified as binary, then a number of METADATA files will be output. The METADATA files contain the spatial domain, grid and map projection specifications and the list of variables and the order in which they appear. For the above example, a file named *MEAN\_NOAH32\_E20RUN\_METADATA.dat* will be created with entries such as the following:

```
DIMENSIONS
east-west          499
north-south        499

Missing value      -9999.000

GRID INFORMATION
MAP_PROJECTION: LAMBERT CONFORMAL
SOUTH_WEST_CORNER_LAT  34.42922
SOUTH_WEST_CORNER_LON -100.6136
TRUELAT1  36.70000
TRUELAT2  36.70000
STANDARD_LON -97.90000
DX  1.000000
DY  1.000000
VARIABLE: Qle          1
VARIABLE: COUNT_Qle      1
```

```

VARIABLE: OBS_Q1e          1
VARIABLE: OBS_COUNT_Q1e    1
VARIABLE: Qh                1
.....
.....

```

This file can be used to determine the order of variables written to the gridded output files.

For NETCDF output, the header of each file contains similar information.

### B.0.2 Stats summary file

The LVT analysis will write out a summary file, for each computed metric with the following name: *MEAN\_SUMMARY\_STATS.dat*. This file can be used to not only determine the domain averaged statistics, but also the order in which variables are written to files. For the above example the file *MEAN\_SUMMARY\_STATS.dat* will contain entries such as the following (The columns 1 to 4 represent the location name, average value for that location, confidence interval, number of points contributing to the average):

```

-----
VAR: Q1e
-----
      ALL:      0.710E+02 +/-      0.492E+01      22
      E1:      0.767E+02 +/-      -              1
      E2:      0.826E+02 +/-      -              1
      E3:      0.421E+02 +/-      -              1
      E4:      0.659E+02 +/-      -              1
.....
.....

-----
VAR: OBS_Q1e
-----
      ALL:      0.906E+02 +/-      0.834E+02      11
      E1:     -0.100E+05 +/-      -              0
      E2:      0.670E+02 +/-      -              1
      E3:     -0.100E+05 +/-      -              0
      E4:      0.496E+02 +/-      -              1
.....
.....

```

```

-----
VAR: Qh
-----
      ALL:      0.151E+02 +/-      0.564E+01      22
      E1:      0.329E+02 +/-      -      1
      E2:     -0.678E+01 +/-      -      1
      E3:      0.164E+02 +/-      -      1
      E4:      0.207E+02 +/-      -      1
.....
.....

```

### B.0.3 ASCII Time Series files

If the extract time series option is enabled for a particular metric in METRICS.TBL, then a corresponding time series file will be generated (similar files will be generated for each location in the *TS\_LOCATIONS.TXT* file).

The time series files with the following names will be generated : *MEAN\_E4.dat*, *RMSE\_E4.dat*

The *MEAN\_E4.dat* file will have entries such as the following:

```

2007 05 02 01 00  qle qle_STD qle_min qle_max qle_ensSTD qle_CI obs_qle obs_qle_STD
obs_qle_min obs_qle_max obs_qle_ensSTD obs_qle_CI qh qh_STD qh_min qh_max qh_ensSTD
qh_CI obs_qh obs_qh_STD obs_qh_min obs_qh_max obs_qh_ensSTD obs_qh_CI

2007 05 02 02 00  qle qle_STD qle_min qle_max qle_ensSTD qle_CI obs_qle obs_qle_STD
obs_qle_min obs_qle_max obs_qle_ensSTD obs_qle_CI qh qh_STD qh_min qh_max qh_ensSTD
qh_CI obs_qh obs_qh_STD obs_qh_min obs_qh_max obs_qh_ensSTD obs_qh_CI
.....
.....

```

The columns represent Time (columns 1-5: year, month, day, hour, minute), mean value, spatial standard deviation, minimum, maximum, ensemble standard deviation, confidence interval of Qle from model (columns 6-11), and mean value, spatial standard deviation, minimum, maximum, ensemble standard deviation, confidence interval of Qle from observations (columns 12-17), and mean value, spatial standard deviation, minimum, maximum, ensemble standard de-

viation, confidence interval of Qh from model (columns 18-23), and mean value, spatial standard deviation, minimum, maximum, ensemble standard deviation, confidence interval of Qh from observations (columns 24-29).

If more variables are included in the analysis, then additional columns will be included for each variable (6 columns per variable).

For metrics such as RMSE (e.g. *RMSE\_E4.dat*, the file entries will be as follows (note that there are no columns for observation values):

```
2007 05 02 01 00 rmse_qlc rmse_qlc_STD rmse_qlc_min rmse_qlc_max
rmse_qlc_ensSTD rmse_qlc_CI
2007 05 02 02 00 rmse_qlc rmse_qlc_STD rmse_qlc_min rmse_qlc_max
rmse_qlc_ensSTD rmse_qlc_CI
.....
.....
```

#### B.0.4 Domain time Series files (Binary/NETCDF)

LVT will output a gridded/tiled output file for each chosen metric, at each stats output interval, if the ‘write time series’ option is enabled (in METRICS.TBL) for that metric. For the above example, files such as the following will be generated.

```
MEAN_TS.200705020000.d01.nc
MEAN_TS.200705030000.d01.nc
MEAN_TS.200705040000.d01.nc
```

```
RMSE_TS.200705020000.d01.nc
RMSE_TS.200705030000.d01.nc
RMSE_TS.200705040000.d01.nc
```

where the timestamp indicates the end time of each analysis interval. For binary output file extension of ‘.gs4r’ will be used instead of ‘.nc’.

#### B.0.5 Final domain files (Binary/NETCDF)

LVT will output a gridded/tiled output file for each chosen metric. For the above example, two final files will be generated with filenames of *MEAN\_FINAL.200705100000.d01.nc* and *RMSE\_FINAL.200705100000.d01.nc*, where the timestamp indicates the end time of the LVT analysis. For NETCDF output file extension of ‘.gs4r’ will be used instead of ‘.nc’.

## References

- [1] S.V. Kumar, C.D. Peters-Lidard, J.A. Santanello, K. Harrison, Y. Liu, and M. Shaw. Land surface verification toolkit (lvt)- a generalized framework for land surface model evaluation. *Geosci. Model Dev.*, pages 869–886, 2012.
- [2] W. Sawyer and A. da Silva. Protex: A sample fortran 90 source code documentation system. Technical report, NASA GMAO, 1997. DAO Office Note 97-11.